

**VISULOX**

# **VISULOX 4**

VISULOX4\_ReferenceCard

28.01.2026

**amitego**



## Table of Contents

1 Events.....	5
2 Script Interface & Variables.....	13
3 Exit Codes.....	18
4 Command Line Parameter.....	23
5 Glossary.....	95

**Limitation of Liability Statement (Disclaimer)**

The Visulox documentation is proprietary to amitego engineering GmbH and no ownership rights are hereby transferred. No part of the documentation shall be used, reproduced, translated, converted, adapted, stored in a retrieval system, communicated or transmitted by any means, for any commercial purpose, including without limitation, sale, resale, licence, rental or lease, without the prior express written consent of amitego engineering.

amitego engineering does not make any representations, warranties or guarantees, express or implied, as to the accuracy or completeness of the documentation. Users must be aware that updates and amendments will be made from time to time to the documentation. It is the user's responsibility to determine whether there have been any such updates or amendments. Neither amitego engineering nor any of its directors, officers, employees or agents shall be liable in contract, tort or in any other manner whatsoever to any person for any loss, damage, injury, liability, cost or expense of any nature, including without limitation incidental, special, direct or consequential damages arising out of or in connection with the use of the documentation.

- Events
  - VISULOX Service Events
  - VISULOX PORTAL Service Events
- Script Interface & Variables
- Exit Codes
- Command Line Parameter
  - VISULOX Command
  - VISULOX PORTAL ATTACH Command
  - VISULOX-PORTAL Command
  - VISULOX-PORTAL OBJECT Command
  - VISULOX-GATEWAY Command
  - Integrity-Check
- Glossary



# 1 Events

## 1.1 VISULOX Service Events

Type	Event	Description	Event variable
Login	Multiple login failures detected	Default warning setting for failed login attempts: 5 per minute, 20 per hour and 50 per day	multipleloginfailures
Login	Access PIN accepted	Login with Access PIN accepted	2faPinAccepted
Login	Access PIN requested	Access PIN for login requested	2faPinRequested
Login	Access PIN rejected	Access PIN was rejected	2faPinRejected
Login	OTP requested	One Time Passcode for login requested	otpRequested
Login (Webtop)	Logged out by supervisor	Application session ended by supervisor via VISULOX Cockpit	webtopSessionEndedByAdmin
Application	Application started	Application session has been started with session controller	sessionControllerStarted
Application	Application started (uncontrolled)	Application session has been started without session controller	sessionUncontrolledStarted
Application	Application ended	Application session ended	sessionControllerEnded

Type	Event	Description	Event variable
Application	Session locked	Application session locked	lock
Application	Session unlocked	Application session unlocked	unlock
Application	Session locked by supervisor	Application session locked by supervisor via VISULOX Cockpit	lockedbyadmin
Application	Session unlocked by supervisor	Application session unlocked by supervisor via VISULOX Cockpit	unlockedbyadmin
Application	Ended by supervisor	Application session ended by supervisor via VISULOX Cockpit	sessionEndedByAdmin
Application	Message sent	Message from supervisor is sent via Cockpit to the user	message
Application	Accepted by user	Message, recording, etc. acknowledged by the user	accept
Application	Rejected	Recording rejected by user	reject
Notification	Notification sent	A notification was sent based on the selected script	scriptsend
Access	Access will expire	Warning, that access to applications will expire soon	
Access	User request	Access requested by the user	accessRequestedByUser
Application	Remark by user	Session annotation created by the user	annotationByUser

Type	Event	Description	Event variable
Application	Remark by supervisor	Annotation created by the supervisor in the VISULOX Cockpit for the session	annotationBySupervisor
Cooperation	Assistance request	Request for a cooperation	assistrequested
Cooperation	Assist observe	Assist mode switched to observe	assistobserve
Cooperation	Assist interact	Assist mode switched to interact	assistinteract
Cooperation	Assist Standby	Assist mode switched to standby	assiststandby
Cooperation	Dual Control	Dual Control cooperation started	dualcontrol
Cooperation	Assistance closed	Cooperation closed	assistclosed
Recording	Manual recording	Manual recording of the session started by the supervisor via VISULOX Cockpit	sessionManuallyRecordingStarted
Recording	Recording stopped	Manual recording stopped by the supervisor via VISULOX Cockpit	sessionManuallyRecordingStopped
Recording	Recording started by Policy	Predefined recording started by Application Policy	sessionRecordingStarted
Keyboard control	In use	Input changed to this user	inputFocusChanged

Type	Event	Description	Event variable
Keyboard control	Inputline	The user entered a line of characters	keyboardControlInputline
Keyboard control	Responsible	Input changed to this user	inputResponsibility
Keyboard control	Idle	Keyboard idle	InputFocusIdle
Keyboard control	Keyboard control started	Keyboard input detection started	keyboardControlStarted
Keyboard control	Keyword detected	Keyword detected by keystroke detection control	keywordDetected
Checkout	Checkout	Session checkout via Cockpit	checkout
Checkout	Checkout with keystrokes	Checkout of the session information in a ZIP file with displayed keystrokes	checkoutwithkeystrokes
Checkout	Report in browser	Report created via Cockpit and displayed in browser	reportGeneratedByGuiBrowser
Checkout	Report via eMail	Report created via Cockpit and sent via eMail	reportGeneratedByGuiEmail
Checkout	Player started	Browser-based player started via Cockpit	player

Type	Event	Description	Event variable
Checkout	Player with keystrokes started	Browser based player with displayed keystrokes started	playerwithkeystrokes
System	Auto accepted	Accepted automatically by the system	autoaccept
System	Auto rejected	Rejected automatically by the system	autoreject
System	Object created	A VISULOX object has been created	objectNew
System	Object copied	A VISULOX object has been copied	objectCopied
System	Object changed	A VISULOX object has been changed	objectChanged
System	Object deleted	A VISULOX object has been deleted	objectDeleted
System	Object attached	A VISULOX object has been attached	objectAttached
System	Object detached	A VISULOX object has been detached	objectDetached
File Transfer	Synced to folder	Files synchronized with the folder	syncput
File Transfer	Synced to Transit Zone	Files synchronized with the Transit Zone	syncget
File Transfer	Transfer to server	File transferred from Transit Zone to the application server via SFTP/FTP	ftput

Type	Event	Description	Event variable
File Transfer	Transfer to Transit Zone	File transferred from application server to the Transit Zone via SFTP/FTP	ftget
File Transfer	Upload (internal web page)	File uploaded via internal web page	webput
File Transfer	Download (internal web page)	File downloaded via internal web page	webget
File Transfer	Upload	File uploaded from client into Transit Zone	userput
File Transfer	Download	File transferred from Transit Zone to the client	userget
File Transfer	File checked	Transferred file has been checked	checked
File Transfer	Approved	Transferred file has been approved	approved
File Transfer	File rejected	File rejected after check	rejected
File Transfer	Pending	File not approved yet	pending
File Transfer	Conditionally accepted	File accepted depending on endpoint rules	tmpaccepted

## 1.2 VISULOX PORTAL Service Events

Type	Event	Description	Event variable
Server	Server started	Server has been started / details	serverStart
Server	Server stopped	Server was stopped / details	serverStop
Server	SSL started	VISULOX PORTAL Security SSL has been started	securitySSLStart
Server	SSL stopped	VISULOX PORTAL Security SSL has been stopped	securitySSLStop
Login	Login rejected	VISULOX PORTAL login was rejected for the user / details	loginResultRejected
Login	Login ambiguous	Login information ambiguous, common name needed	loginResultAmbiguous
Login	Anonymous login not supported	Login failed, Anonymous login not supported	loginResultAnonymous
Login	Unresolvable user	Login failed, unresolvable user	loginResultUnresolvable
Workspace	Workspace opened	Workspace session has been started / details	webtopSessionStartedDetails
Workspace	Workspace closed	Workspace session has been stopped / details	webtopSessionEndedDetails
Application	Application session started	Application session has been started / details	sessionStartedDetails


Type	Event	Description	Event variable
Application	Application session stopped	Application session was stopped / details	sessionEndedDetails
VISULOX PORTAL Object	Object modified	VISULOX PORTAL object has been changed	modifySuccess
VISULOX PORTAL Object	Object created	A new VISULOX PORTAL object was created	createSuccess
VISULOX PORTAL Object	Object create failed	Creating an VISULOX PORTALobject failed	createFailure
VISULOX PORTAL Object	Rename successful	VISULOX PORTAL object renamed successfully	renameSuccess
VISULOX PORTAL Object	Object deleted	An VISULOX PORTAL object was deleted	deleteSuccess

## 2 Script Interface & Variables

### 2.1 Available script categories


Category	Used as
Notification	These action scripts can be chosen, where application notifications are used (Application Policy).
Pin	These action scripts deliver information for the Multi Factor Authentication (Login Policy).
Report	These are report actions scripts.
Validate	These action scripts can be chosen for validation.
*	These action scripts are available everywhere scripts can be used. The setup provides one script in this category, which allows to dump all variables provided to an action script. This is helpful for testing.

#### Notification script variables (examples)

 The following list contains some useful examples for script variables.  
To get the complete list of available variables for a certain action script, the dump script should be used.


Variable	Description
VLXFULLNAME	Full name of the user

Variable	Description
VLXSURNAME	Surname of the user
VLXEMAIL	eMail address of the user
VLXSMS	SMS address of the user
VLXOWNER	Owner of the application
VLXGROUPLIST	Group list
VLXUSERPROFILE	Profile of the user
VLXPIN	PIN for Multi Factor Authentication
VLXPIN_FMT	Formatted PIN for Multi Factor Authentication
VLXPIN_SEQUENCE	Sequence number for PIN
VLXPIN_EXPIRATIONTIME	Expiration time with date for the PIN
VLXPIN_LIFETIME	Lifetime for the PIN
VLXPIN_TEXT	PIN text



<b>Variable</b>	<b>Description</b>
VLXACCESSPOIN	Access Point
VLXCREATETIME	Creation time
VLXLOG	Path to logs
VLXLOGINUSER	Logged in user
VLXMANAGER	Manager of the user
VLXObject	Name of the object
VLXOWNERID	Owner ID
VLXOWNERSHORT	Short name of the owner
VLXPOLICY	VISULOX policy
VLXREMOTEIP	Remote IP
VLXSMS	SMS of the user
VLXLISTHASH	Hash

Variable	Description
VLXCLIENTIP	Client IP address
VLXLANG	Language
VLXSESSIONHOST	Host, where the session was started
VLXCREATETIME_FMT	Time of creation (readable)
VLXSESSIONSTARTTIME	Start time of the session
VLXSESSIONDURATION	Duration of the session
VLXSESSIONDURATION_FMT	Duration of the session (readable)
VLXSESSIONENDTIME	Endtime of the session
VLXSESSIONENDTIME_FMT	Endtime of the session (readable)
VLXAPPLICATION	Application name
VLXRECIPIENT	Recipient
VLXTICKETID	Ticket ID of the user



Variable	Description
VLXLOGINSCRIPT	Login script
VLXAPPLICATIONUSER	User of the application
VLXBADWORD	Detected keyword in Keyboard recording
VLXEVENTINFO	Event info
VLXCREATEDBY	Created by
VLXCREATEDBYSHORT	Short name of creator

**See also:**

- [Variables in notifications](#)
- [Transit script variables](#)
- [How to control action scripts from the command line](#)

### 3 Exit Codes

In the following table all VISULOX Exit Codes are listed with a short description and the meaning of the code.

Exit code	Short description	Comment
0	SUCCESS	Success
1	FAILURE	Failure
2	WARNING	Warning
3	REJECT	Policy
4	ACCEPT	Policy
5	PASSON	Policy
6	APPLY	Policy
7	EXCLUDE	Policy
8	APPROVAL	Rule
9	ALLOW	Rule
10	ALLOWSPONTAN	Rule

<b>11</b>	ALLOWENDPOINT	Transit rule matches, but endpoint has to be taken into account
<b>12</b>	DENY	Deny action
<b>13</b>	DENYTOOLARGE	Transit: file is too large
<b>14</b>	DENYDIRECTION	Transit: file can not be transferred in this direction
<b>15</b>	DENYFORENDPOINT	Transit: file cannot be handled with this endpoint
<b>16</b>	DENYVIRUS	Transit: file has a virus
<b>17</b>	DENYEMPTY	Transit: file is empty
<b>18</b>	DENYPASSON	Transit: script denies Passon
<b>19</b>	NOMATCHPOLICY	Policy
<b>20</b>	USAGE	Command line usage error
<b>21</b>	DATAERR	Data format error
<b>22</b>	NOINPUT	Cannot open input
<b>23</b>	UNKNOWNUSER	User unknown

<b>24</b>	UNKNOWNHOST	Host name unknown
<b>25</b>	UNAVAILABLE	Service unavailable
<b>26</b>	SOFTWARE	Internal software error
<b>27</b>	LICENSE	License error
<b>28</b>	OSERR	System error (e.g. can't fork)
<b>29</b>	OSFILE	Critical OS file missing
<b>30</b>	CANTCREAT	Can't create (user) output file
<b>31</b>	IOERR	Input/output error
<b>32</b>	TEMPFAIL	Temp failure; user is invited to retry
<b>33</b>	PROTOCOL	Remote error in protocol
<b>34</b>	NOPERM	Permission denied
<b>35</b>	CONFIG	Configuration error
<b>36</b>	INIT	Initialization error


<b>37</b>	SCRIPTERROR	Script execution with error
<b>38</b>	DATABASE	Error during database interaction
<b>39</b>	TIMEOUT	Timeout
<b>40</b>	REGISTRATION	Error on registration
<b>41</b>	XAUTH	Error on setting x11 cookie
<b>42</b>	ZMQERROR	ZeroMQ error
<b>43</b>	CRYPTOERROR	Crypto error
<b>44</b>	STARTREJECTED	Start rejected
<b>45</b>	ALREADYRUNNING	Program already running
<b>46</b>	NOTIMPLEMENTED	Not implemented
<b>47</b>	UNDEFINED	Operation has no defined state yet
<b>48</b>	EXHAUSTED	No resource available anymore
<b>49</b>	LOOKUP	Item not found

<b>50</b>	EMPTY	Unexpected empty result
<b>51</b>	RESTART	Restarting...
<b>52</b>	RETRY	Try again
<b>53</b>	OLDREQUEST	Received reply to a previous request
<b>54</b>	TRANSPORT	Error in transport layer
<b>55</b>	QUORUM	No etcd leader
<b>56</b>	ACCESSPOINTCHECK	Access validation
<b>57</b>	BUSY	Resource temporarily unavailable
<b>100</b>	ACCESSREQUEST	Access Policy Request
<b>200</b>	DISABLED	LDAP cannot get data, because the datasource is disabled
<b>210</b>	APPROVALPASSON	Rule
<b>1000</b>	INFO	Info line in integrity test

## 4 Command Line Parameter

### 4.1 VISULOX Command

```
visulox <command> [<command-specific args>]
```

 During installation **/usr/sbin/visulox** is created, which makes it possible to execute the VISULOX Service Command without using the whole path.

#### 4.1.1 Available parameters

Command	Description	Additional commands / args
addon	Command Line Interface to VISULOX Addons	cmdconnect, cmdguard, ftclient, host, script, template
admin	Manage the VISULOX Administration	cockpit, action, message, region, timeprofile
archive	Manage VISULOX Archive Node	-node <>, -set
assignments	Check assignments in policies and applications	app, datastore, policy
attach	Attach a node to the VISULOX Cluster	<hostname>, -location, -zone
cluster	Builds a VISULOX Cluster	data, layout, build -f <>   -template

Command	Description	Additional commands / args
cockpit	Start of the VISULOX Cockpit	title <>, lang <>, roles <>, grant <>, groupaccess <>,owner <>, ksr, cdm, kiosk, personal
config	Manage the VISULOX configuration	accesspoint, datasources, dump, edit, env, list, locations,logo, mynodename, rebuild, reset, vap
database	Query the VISULOX Database	list, backup, restore, fields, query, integrity, status -vacuum, rename <>, node <>, table <>, timeout <>
datasource	Manage the VISULOX Datasources	add, check, copy, delete, edit, list
detach	Detach a node from the VISULOX Cluster	server <>, timeout <>
end2end	VISULOX end2end check	off, on, status
etcd	Manage ETCD instances	benchmark, client, del, get, instance, member, node, put, test
export	Export from VISULOX	events, files, sessions
integrity	VISULOX Integrity-Check	sys, lib, cmd, users, portal, ulimit, store, recorder, datasources, license
license	Manage the VISULOX License	list, replace, test, usage (-component <users sessions recorders hostcontrols> -unit <week month year>)
log	Query VISULOX log database	since <>, until <>, loglevel <>, follow

Command	Description	Additional commands / args
online	VISULOX online status	getpin, fields (list available fields), -i (ignore case), -object <> (owner or group mask), -application <>, -fields <>, sortby <> (sort by field)
otp	Manage the VISULOX OTP configuration	check <>, key, reset <>, set <>
passcache	Manage the VISULOX Passcache	list, fields, edit, delete
ping	Ping local master or designated worker	id <> (outdated)
policy	Command line interface to the VISULOX Policies	external, login, internal, access, application, transit
portal	Attach / detach VISULOX Service from VISULOX PORTAL Service (See also: <a href="#">VISULOX PORTAL ATTACH Command</a> )	array, config, discover, drop, admin, mode, etc (see: <a href="#">VISULOX-PORTAL Command</a> ) visulox portal --help shows all available VISULOX PORTAL and VISULOX commands. With visulox portal admin -user <unixuser> a Unix user can be activated as VISULOX Portal Admin (⚠ It is recommended to set a different user than root!)
pwdmgmt	Manage / list account passwords	expired, mustchange, notify <>, warn
report	Command line interface to VISULOX Report	title <>, mctitle <>, name <>, type <>, xslt <>, metadata <>, query <>, tframe <>, -from<>. -to <>, sql <>, lang <>, filename <>, mailto <>, mailsubject <>, maildescription <>, maildescriptionfile <>, archive <>

Command	Description	Additional commands / args
reset	Reset local cluster state	
restart	Restart VISULOX Service (locally) <div style="border: 1px solid red; padding: 5px; margin-top: 10px;">❌ Use with caution, all sg, sc and scx will be stopped.</div>	-service <>, -timeout <>
start	Start VISULOX Service (locally)	debug
status	Query VISULOX status	diskfree, features, load, monitor, next, servers, services, sessions, uptime, usage, users, workers, server <>, serverfilter <>, print, fields <>
stop	Stop VISULOX Service (locally)	id <>
store	Manage the VISULOX store	attach, changed, detach, disable, enable, extras, get, migrate, missing, next, put, status, slot <>
support	Gather information for support (-info: short report)	directory <>, sys, dump, etc, rt, logs, net, integrity, config, tta
transit	Command line interface to VISULOX Transit Zone (list, import)	list, import, owner, path, rtime
version	Display versions of installed VISULOX packages	

**i** With **-help** or **-?** the detailed options for a basic command can be displayed.

If more parameters are needed for a command, the available options are always displayed by entering the basic command.

### 4.1.2 General commands

Parameter	Description
-format <value>	Format of output (text,xml,csv,json,tcl) / Default: <text>
-log <value>	Set loglevel to error, verbose, info or debug / Default: <>
-verbose	More messages on stdout
-run	Run an operation (use only on application request)
-stdin	Get arguments from stdin
--	Forcibly stop option processing
-help / -?	Display commands

### 4.1.3 Usage

The following examples show the usage of the VISULOX Service Command:

### Show VISULOX status

```
visulox status
```

### Show license information

```
visulox license
```

### Replace license

```
visulox license replace -file <path to license file>
```

### List sessions

```
visulox status sessions  
visulox online
```

### List unassigned applications

```
visulox database query -sql "select vlxapplication from external_applications WHERE vlxapplicationgroups = '' AND  
vlxapplicationusers = ''" -format csv -raw
```

### Transit import & list

```
visulox transit import -path /tmp/file.txt -owner "o=Tarantella System Objects/cn=TestUser"
```

```
visulox transit list -owner "o=Tarantella System Objects/cn=TestUser"
```

### Detach VISULOX Node

```
visulox detach <vlx-node.domain>
```

## 4.2 VISULOX PORTAL ATTACH Command

```
visulox portal attach [<command-specific args>]
```

**i** During installation **/usr/sbin/visulox** is created, which makes it possible to execute the VISULOX Service Command without using the whole path.

### 4.2.1 Available parameters

Command	Description
-all	Install all (default)
-portal	Modify VISULOX PORTAL only, write configuration
-examples	setup examples
-attach	Attach VISULOX Service to VISULOX PORTAL Service

Command	Description
-expect	Install expect script only
-webtop	Install webtop script only
-jspconfig	Create VISULOX JSP configuration file
-apacheport <value>	Local port to address Apache. If empty, discovered by webservice configuration <>
-externalport <value>	External port to address Apache. If empty, discovered by httpd.conf <>
-serviceonline <value>	Enable/disable Webtop Enhancements <true>
-adminuser <value>	UNIX user for the VISULOX webservice user in VISULOX PORTAL<vlxwebservice> <b>Deprecated!</b> Configuration parameter <b>portal.admin.user</b> should be used instead.
-adminuid <value>	User ID for the VISULOX admin user in VISULOX PORTAL <610> <b>Deprecated!</b> Configuration parameter <b>portal.admin.uid</b> should be used instead.
-adminpwd <value>	Password for the VISULOX admin user in VISULOX PORTAL <generate>
-adminou <value>	OrgUnit for Webservice user cn=<host name>/<adminou> <>
-version <value>	Force VISULOX PORTAL version <>

## 4.2.2 General commands

Parameter	Description
-format <value>	Format of output (text,xml,csv,json,tcl) / Default: <text>
-verbose	More messages on stdout
-run	Run an operation (use only on application request)
--	Forcibly stop option processing
-help / -?	Display commands

## 4.2.3 Usage

The following examples show the usage of the attach command:

### Attaching VISULOX Service to VISULOX PORTAL Service

```
visulox portal attach
```

This command checks if login-ens is enabled. If this is the case a local user vlxwebservice (610) with group ttaserv (500) was added to the system. A password was also generated and stored secure.

## 4.3 VISULOX-PORTAL Command

```
visulox-portal <command> [<command-specific args>]
```

**i** During installation **/usr/sbin/visulox-portal** is created, which makes it possible to execute the VISULOX PORTAL Service Command without using the whole path.

### 4.3.1 Available parameters

Command	Description
array	Creates and manages arrays of VISULOX PORTAL servers
config	Edits array-wide and server-specific configuration
discover	Discover available resources
drop	Drop discovered resources
emulatorsession	Lists and controls emulator sessions
gateway	Manipulates the VISULOX GATEWAY store
help	Displays this list of commands
info	Shows status information for the local server

<b>Command</b>	<b>Description</b>
object	Manipulates objects in the datastore
passcache	Manipulates the password cache
restart	Restarts VISULOX PORTAL services
role	Configures role occupants and their extra webtop links
security	Controls security services, manages certificates
serverrename	Change the server's peer or external DNS name
service	Edits service object configuration
start	Starts VISULOX PORTAL services
status	Shows the current status of VISULOX PORTAL array members
stop	Stops VISULOX PORTAL services
tokencache	Manipulates the token cache
version	Displays versions of installed VISULOX PORTAL packages

Command	Description
webserver	Controls the VISULOX PORTAL Web Server
webtopsession	Lists and controls webtop sessions

**i** With **visulox-portal <subcommand> --help** the detailed options for a command can be displayed. If more parameters are needed for a command, the available options are always displayed by entering the basic command.

### 4.3.2 Usage

The following examples show the usage of the VISULOX-PORTAL Command:

#### Show VISULOX PORTAL status

```
visulox-portal status
```

#### Show version information

```
visulox-portal version
```

#### List webtop sessions

```
visulox-portal webtopsession list
```

### List VISULOX Array members

```
visulox-portal array list
```

### Join VISULOX Array member

```
visulox-portal array join --primary <hostname> --secondary <hostname>
```

## 4.4 VISULOX-PORTAL OBJECT Command

- [visulox-portal object](#)
- [Naming Objects in the Organizational Hierarchy](#)
- [visulox-portal object add\\_host](#)
- [visulox-portal object add\\_link](#)
- [visulox-portal object add\\_member](#)
- [visulox-portal object delete](#)
- [visulox-portal object edit](#)
- [visulox-portal object list\\_attributes](#)
- [visulox-portal object list\\_contents](#)
- [visulox-portal object new\\_charapp](#)
- [visulox-portal object new\\_container](#)
- [visulox-portal object new\\_dc](#)
- [visulox-portal object new\\_doc](#)
- [visulox-portal object new\\_group](#)
- [visulox-portal object new\\_host](#)
- [visulox-portal object new\\_org](#)
- [visulox-portal object new\\_orgunit](#)
- [visulox-portal object new\\_person](#)

- visulox-portal object new\_windowsapp
- visulox-portal object new\_xapp
- visulox-portal object remove\_host
- visulox-portal object remove\_link
- visulox-portal object remove\_mapping
- visulox-portal object remove\_member
- visulox-portal object rename
- visulox-portal object script

#### 4.4.1 visulox-portal object

The visulox-portal object command enables you to create, list, edit, and delete objects in the organizational hierarchy.

You can also add and remove assigned applications links, configure application server load balancing for each application, and add and remove group members.

##### Syntax

```
visulox-portal object add_host | add_link | add_mapping | add_member |  
delete | edit | list_attributes | list_contents | new_charapp | new_container |  
new_dc | new_doc | new_dynamicapp | new_group | new_host | new_org |  
new_orgunit | new_person | new_windowsapp | new_xapp | remove_host |  
remove_link | remove_mapping | remove_member | rename | script
```

##### Description

Available subcommands for this command.

add_host	Adds application servers to the list of those that can run an application.
add_link	Adds assigned applications links.
add_member	Adds members to a group.

delete	Permanently deletes objects from the organizational hierarchy.
edit	Edits attributes <b>for</b> an object
list_attributes	Lists attributes of an object.
list_contents	Lists the contents of container object, such as an OU or an organization.
new_charapp	Creates character application objects.
new_container	Creates Active Directory container objects.
new_dc	Creates domain component objects.
new_doc	Creates document objects.
new_group	Creates group objects
new_host	Creates application server objects.
new_org	Creates organization objects.
new_orgunit	Creates organizational unit objects.
new_person	Creates user profile objects.
new_windowsapp	Creates Windows application objects.
new_xapp	Creates X application objects
remove_host	Removes application servers from those that can run an application.
remove_link	Removes assigned applications links
remove_mapping	Removes mappings <b>for</b> a dynamic application
remove_member	Removes members from groups.
rename	Renames or moves an object.
script	Runs a batch script of object commands

 All commands include a **--help** option. You can use **visulox-portal object subcommand --help** to get help on a specific command.

## Examples

The following example lists the objects that belong to the organizational unit Sales.

```
visulox-portal object list_contents --name "o=Example/ou=Sales"
```



## Naming Objects in the Organizational Hierarchy

When an object is created in the VISULOX Portal Console, any characters can be chosen for the name of the object, apart from backslash (\) or plus (+).

On the command line, if a forward slash is used in an object name, backslash protect is needed, or it has to be escaped. This is because VISULOX Portal interprets the forward slash as a part of the organizational hierarchy.

For example, if an object should be created with the relative name `cn=a/b` beneath `o=organization`, the portal tries to create an object called `b` within `o=organization/cn=a`.

This fails because `o=organization/cn=a` does not exist. To create an object with this name, enter `cn=a\b`.

On the command line, if the name of an object includes spaces, make sure the name is enclosed in quotes, for example `".../_ens/o=Example Organization"`.

With the `tarantella object` command, any name in the local repository is treated as case insensitive.

When you create or rename an object, the case used is preserved. However, other commands, such as the `tarantella webtopsession` and `tarantella emulatorsession` commands, are case sensitive.

### 4.4.2 visulox-portal object add\_host

Adds application servers to the list of those that can run an application, for application server load balancing.

#### Syntax

```
visulox-portal object add_host { --name obj... --host hobj... } | --file file
```

#### Description

Available options for this command.

```
--name The names of application objects you want to configure load balancing for.
--host The names of application server objects you want to add to the load balancing pool.
--file A file containing a batch of commands to configure application server load balancing.
```

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

## Examples

The following example adds the application server rome to the load balancing pool for the application Slide-o-Win.

```
visulox-portal object add_host --name "o=applications/cn=Slide-o-Win" --host "o=appservers/ou=Sales/cn=rome"
```

The following example adds the group WinHosts to the load balancing pool for the applications Write-o-Win and Slide-o-Win. Load balancing is performed across all the application servers in WinHosts.

```
visulox-portal object add_host --name "o=applications/cn=Write-o-Win" "o=applications/cn=Slide-o-Win" --host "o=appservers/cn=WinHosts"
```

### 4.4.3 visulox-portal object add\_link

Adds assigned applications links for an object.

## Syntax

```
visulox-portal object add_link { --name obj... --link lobj... } | --file file
```

## Description

Available options for this command.

```
--name The names of objects you want to add assigned applications links for.
--link The names of assigned applications links you want to add.
--file A file containing a batch of commands to add assigned applications links.
```

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

## Examples

The following example adds the Write-o-Win application to Violet Carson's assigned applications.

```
visulox-portal object add_link --name "o=Example/ou=Sales/cn=Violet Carson" --link "o=applications/cn=Write-o-Win"
```

The following example adds the group Applications to the assigned applications of the organizational units Sales and Marketing. Everyone who inherits assigned applications from one of these OUs, for example, they belong to that OU and inherit assigned applications from parent is selected for their user profile object, sees all the applications in the group in their assigned applications.

```
visulox-portal object add_link --name "o=Example/ou=Sales" --name "o=Example/ou=Marketing" --link "o=applications/cn=Applications"
```

### 4.4.4 visulox-portal object add\_member

Adds objects to groups.

#### Syntax

```
visulox-portal object add_member { --name obj... --member mobj... } | --file file
```

## Description

Available options for this command.

```
--name      Specifies the names of group objects you want to add members for.
--member    Specifies the names of objects you want to add to the groups.
--file      Specifies a file containing a batch of commands to add group members.
```

Make sure you quote any object names containing spaces, **for** example, "o=Example Organization".

## Examples

The following example adds the Write-o-Win application to the group Applications.

```
visulox-portal object add_member --name "o=applications/cn=Applications" --member "o=applications/cn=Write-o-Win"
```

The following example adds the three application server objects rome, brussels, and berlin to the group WinHosts.

This group can be added to an application's Hosting applications Servers Tab to perform load balancing between the application servers.

From the command line, use visulox-portal object add host.

```
visulox-portal object add_member --name "o=appservers/cn=WinHosts" --member "o=appservers/ou=Sales/cn=rome" \  
"o=appservers/cn=brussels" "o=appservers/ou=Marketing/cn=berlin"
```

### 4.4.5 visulox-portal object delete

Permanently deletes objects from the organizational hierarchy.

## Syntax

```
visulox-portal object delete { --name obj [ --children ] } | --file file
```

## Description

Available options for this command.

```
--name      Specifies the name of the object you want to delete.
--children  When deleting organizational units, Active Directory containers or domain components, confirms that you want to delete the object and all objects that belong to it, recursively. As a safeguard, it is impossible to delete an organizational unit, Active Directory container or domain component without specifying --children.
--file      Specifies a file containing a batch of commands to delete objects.
```

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

## Examples

The following example removes the user profile object for Violet Carson.

```
visulox-portal object delete --name "o=Example/ou=Sales/cn=Violet Carson"
```

The following example deletes the organizational unit Sales.

```
visulox-portal object delete --name "o=Example/ou=Sales" --children
```

## 4.4.6 visulox-portal object edit

Edits the attributes of an object in the organizational hierarchy.

### Syntax

```
visulox-portal object edit { --name obj { --attribute [value] }... } | --file file
```

### Description

Available options for this command.

<code>--name</code>	Specifies the name of the object you want to edit the attributes of.
<code>{--attribute [value]}...</code>	Specifies the attribute names you want to edit, and their <b>new</b> values. The valid attributes depend on the type of object. See the <code>visulox-portal object new_object_type</code> documentation <b>for</b> the appropriate list. For example, when editing attributes <b>for</b> an application object you can specify <code>--displayusing</code> to edit the attribute. If you omit value <b>for</b> an attribute, it is deleted from the object.
<code>--file</code>	Specifies a file containing a batch of commands to edit attributes.

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

### Examples

The following example changes the “Inherit Assigned Applications from Parent” attribute for the organizational unit Sales.

```
visulox-portal object edit --name "o=Example/ou=Sales" --inherit false
```

## 4.4.7 visulox-portal object list\_attributes

Lists the attributes of an object in the organizational hierarchy.

### Syntax

```
visulox-portal object list_attributes { --name obj [ --attribute... ]} | --file file
```

### Description

Available options for this command.

<code>--name</code>	Specifies the name of the object you want to list the attributes of.
<code>{--attribute [value]}...</code>	Specifies the attribute names you want to list. The valid attributes depend on the type of object. See the <code>visulox-portal object new_object_type</code> documentation <b>for</b> the appropriate list. For example, when listing attributes <b>for</b> an application object you can specify <code>--displayusing to edit</code>
the attribute.	
<code>--file</code>	Specifies a file containing a batch of commands to list attributes.

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

### Examples

The following example lists all attributes for the Sales organizational unit.

```
visulox-portal object list_attributes --name "o=Example/ou=Sales"
```

The following example lists the Email Address and Login attributes for the user profile object for Rusty Spanner.

```
visulox-portal object list_attributes --name "o=Example/ou=IT/cn=Rusty Spanner" --email -enabled
```

#### 4.4.8 visulox-portal object list\_contents

Lists the objects that belong to a container object in the organizational hierarchy, such as an organization or organizational unit (OU).

##### Syntax

```
visulox-portal object list_contents { --name obj }| --file file
```

##### Description

Available options for this command.

```
--name Specifies the name of the object you want to list the contents of.  
--file Specifies a file containing a batch of commands to list object contents.
```

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

##### Examples

The following example lists all the objects within the organizational unit Sales.

```
visulox-portal object list_contents --name "o=Example/ou=Sales"
```

#### 4.4.9 visulox-portal object new\_charapp

Creates one or more character application objects.

##### Syntax

```
visulox-portal object new_charapp {  
  --name obj  
  --emulator scocon|vt420|wyse60  
  --termtype type  
  --width pixels  
  --height pixels  
  [ --description text ]  
  [ --app pathname ]  
  [ --args args ]  
  [ --appserv obj... ]  
  [ --method telnet|ssh ]  
  [ --resumable never|session|always ]  
  [ --maxinstances 0|instances ]  
  [ --displayusing independent|kiosk ]  
  [ --maximize true|false ]  
  [ --cols cols ]  
  [ --lines lines ]  
  [ --icon icon_name ]  
  [ --hints hint... ]  
  [ --font courier|helvetica|timesroman ]  
  [ --fontsize points ]
```

```
[ --fixedfont true|false ]
[ --autowrap true|false ]
[ --cursor off|block|underline ]
[ --statusline none|indicator|hostmessages|standard|extended ]
[ --scrollstyle line|multiple|smooth ]
[ --border normal|indented|raised ]
[ --answermsg message ]
[ --appkeymode true|false ]
[ --keypad numeric|application ]
[ --cursorkeys application|cursor ]
[ --escape 7-bit|8-bit ]
[ --codepage 437|850|852|860|863|865|8859-1|8859-2|Multinational|Mazovia|CP852 ]
[ --ldapusers user_dn... ]
[ --ldapgroups group_dn... ]
[ --ldapsearch search_string... ]
[ --loadbal default|cpu|memory|sessions ]
[ --compression automatic|on|off ]
[ --env setting... ]
[ --login script ]
[ --keymap keymap ]
[ --attributemap attrmap ]
[ --colormap colormap ]
[ --resumetimeout mins ]
[ --windowclose suspendsession|endsession ]
[ --ssharguments args ]
} | --file file
```

## Description

Available options for this command.

```
--name          The common name of the object in the datastore.
--emulator      The type of emulation required for the application.
```

--termtypes The terminal type required **for** the application.  
--width The width of the application, in pixels.  
--height The height of the application, in pixels.  
--description A text description of the object.  
--app Full path name of the application.  
--args The command-line arguments to use when starting the application.  
--appserv The application servers that can run the application.  
--method The mechanism used by the VISULOX Portal server to access the application server and start the application.  
--resumable Resumability behavior **for** the application.  
--maxinstances The maximum number of instances of the application a user can run simultaneously.  
--displayusing How the application is displayed to the user.  
--maximize The initial size of the application.  
--cols The number of columns in the terminal window.  
--lines The number of lines in the terminal window.  
--icon Workspace icon **for** the application.  
--hints String containing additional name-value data **for** the application.  
--font Determines the font family used within the terminal window **for** the application.  
--fontsize Defines the font size in the terminal window.  
--fixedfont Uses the font size specified by --fontsize **for** the terminal window.  
--autowrap Determines the behavior when a user types characters extending beyond the right edge of the terminal window.  
--cursor Cursor style used **for** the application.  
--statusline Specifies the type of status line.  
--scrollstyle The scroll behavior of the terminal window.  
--border The border style **for** the terminal window.  
--answermsg Defines the message to **return** when an inquiry is sent from the application server to the emulator.  
--appkeymode Determines whether the application can change the codes generated by keys on the keyboard.  
--keypad Specifies the behavior of the cursor keys  
--cursorkeys Specifies the behavior of the cursor keys.  
--escape Specifies how escape sequences are sent from the emulator to the application server.  
--codepage The code page to use **for** the emulator.  
--ldapusers Assigns the application to the specified LDAP users.  
--ldapgroups Assigns the application to the specified LDAP groups.  
--ldapsearch Assigns the application to the users that match the LDAP search criteria.  
--loadbal Load balancing algorithm to use.

```
--compression  Whether the AIP protocol compresses commands for transmission.
--env          Environment variable settings needed to run the application.
--login       The login script used to start the application.
--keymap      Path name of a keyboard map file.
--attributemap  The attribute map to use for the application.
--colormap    The color map to use for the application.
--resumetimeout  Number of minutes the application is resumable for.
--windowclose Effect on application session of closing the main application window.
--ssharguments Command-line arguments for the ssh client.
--file        Batch file used to create multiple objects within the organizational hierarchy.
```

To batch-create multiple objects, use the --file option. Use the other options to create a single object.

## Examples

The following example creates a character application object for the application Pers-o-dat.

The application can be run on the application servers prague and london. Application server load balancing decides which application server to use.

```
visulox-portal object new_charapp --name "o=applications/cn=Pers-o-dat" --emulator vt420 --termtype vt220 \  
--width 400 --height 300 --app /bin/persodat --appserv "o=appservers/cn=prague" "o=appservers/ou=IT/cn=london"
```

### 4.4.10 visulox-portal object new\_container

Creates one or more Active Directory container objects.

#### Syntax

```
visulox-portal object new_container { --name obj } | --file file
```

## Description

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new Active Directory container object with name Users, within the [example.com](#) domain components.

```
visulox-portal object new_container --name "dc=com/dc=example/cn=Users"
```

The following example creates two Active Directory container objects using a batch script defined as a “here-document”. You can alternatively store the batch script in a file, and reference it using `--file filename`.

```
visulox-portal object new_container --file - <<EOF
--name "dc=com/dc=example/cn=Users"
--name "dc=com/dc=example/cn=Applications"
EOF
```

### 4.4.11 visulox-portal object new\_dc

Creates one or more domain component objects.

## Syntax

```
visulox-portal object new_dc { --name obj } | --file file
```

## Description

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new domain component object with name `com`, at the top level of the organizational hierarchy.

```
visulox-portal object new_dc --name "dc=com"
```

The following example creates two domain component objects using a batch script defined as a “heredocument”.

You can alternatively store the batch script in a file, and reference it using `--file filename`.

```
visulox-portal object new_dc --file - <<EOF
--name "dc=com"
--name "dc=com/dc=example"
EOF
```

### 4.4.12 visulox-portal object new\_doc

Creates one or more document objects.

## Syntax

```
visulox-portal object new_doc {
--name obj
```

```
--url url
[ --description text ]
[ --newbrowser true|false ]
[ --icon icon_name ]
[ --hints hint...]
[ --ldapusers user_dn... ]
[ --ldapgroups group_dn... ]
[ --ldapsearch search_string... ]
} | --file file
```

## Description

Available options for this command.

<code>--name</code>	The name of the document object.
<code>--url</code>	URL displayed when document object link is clicked.
<code>--description</code>	A text description of the object.
<code>--newbrowser</code>	Displays the document in a <b>new</b> browser window.
<code>--icon</code>	Workspace icon <b>for</b> the application.
<code>--hints</code>	String containing additional name-value data <b>for</b> the application.
<code>--ldapusers</code>	Assigns the application to the specified LDAP users.
<code>--ldapgroups</code>	Assigns the application to the specified LDAP groups.
<code>--ldapsearch</code>	Assigns the application to the users that match the LDAP search criteria.
<code>--file</code>	A file containing a batch of commands to configure application server load balancing.

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new document object named PhoneList.

```
visulox-portal object new_doc \
```

```
--name "o=applications/ou=Finance/ou=Administration/cn=Phone List" \  
--url http://newyork.example.com \  
--newbrowser false
```

The following example creates two document objects using a batch script defined as a “here-document”. You can alternatively store the batch script in a file, and reference it using `--file filename`.

```
visulox-portal object new_doc --file - <<EOF  
--name "o=applications/ou=Finance/ou=Administration/cn=Phone List"  
--url http://newyork.example.com  
--newbrowser false  
--name "o=applications/cn=Example web site"  
--url http://www.example.com  
--newbrowser true  
EOF
```

### 4.4.13 visulox-portal object new\_group

Creates one or more group objects.

#### Syntax

```
visulox-portal object new_group {  
--name obj  
[ --description text ]  
[ --member obj... ]  
[ --ldapusers user_dn... ]  
[ --ldapgroups group_dn... ]
```

```
[ --ldapsearch search_string... ]  
} | --file file
```

## Description

Available options for this command.

```
--name           The name of the group object.  
--description    A text description of the object.  
--member         Member of the group object.  
--ldapusers      Assigns the application to the specified LDAP users.  
--ldapgroups     Assigns the application to the specified LDAP groups.  
--ldapsearch     Assigns the application to the users that match the LDAP search criteria.  
--file           A file containing a batch of commands to configure application server load balancing.
```

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new group object with common name WinHosts, belonging to the organization object appservers. The group's members are the application server objects for the application servers rome, brussels, and berlin.

```
visulox-portal object new_group --name "o=appservers/cn=WinHosts" \  
--member "o=appservers/ou=Sales/cn=rome" "o=appservers/cn=brussels" \  
"o=appservers/ou=Marketing/cn=berlin"
```

The following example creates three group objects using a batch script defined as a “here-document”. The groups have no members. You can use “visulox-portal object add member” to add members

later from the command line. You can alternatively store the batch script in a file, and reference it using `--file filename`.

```
visulox-portal object new_group --file - <<EOF
visulox-portal object new_host
--name "o=appservers/cn=WinHosts"
--name "o=appservers/cn=UNIXHosts"
--name "o=applications/cn=Applications"
EOF
```

#### 4.4.14 visulox-portal object new\_host

Creates one or more of the following objects:

- Application server.
- Dynamic application server.
- Oracle VM hypervisor host.
- VirtualBox hypervisor host.

#### Syntax

For an application server object, use the following syntax:

```
visulox-portal object new_host {
--name obj
[ --address address ]
[ --description text ]
[ --ntdomain dom ]
[ --available true|false ]
[ --auth trytta|nevertrytta|default ]
[ --location location ]
[ --hostlocale ll_tt ]
[ --maxcount count ]
```

```
[ --userassign spec ]  
[ --sgdpermittedauthtypes types ]  
} | --file file
```

For a dynamic application server object, use the following syntax:

```
visulox-portal object new_host {  
  --name obj  
  --dynamic  
  [ --description text ]  
  [ --auth trytta|nevertrytta|default ]  
  [ --vsbclass classname ]  
  [ --vsbparams params ]  
  [ --sgdpermittedauthtypes types ]  
} | --file file
```

For an Oracle VM hypervisor host object, use the following syntax:

```
visulox-portal object new_host {  
  --name obj  
  --address address  
  --ovm  
  [ --description text ]  
  [ --available true|false ]  
  [ --auth trytta|nevertrytta|default ]  
  [ --vmsubnet network-address/mask ]  
  [ --ovmtags tag... ]  
  [ --ovmpools pool... ]  
  [ --ovmservers server-name... ]  
  [ --vmnames vm-name... ]  
  [ --vmostypes os-type... ]
```

```
[ --maxcount count ]
[ --userassign spec ]
[ --sgdpermittedauthtypes types ]
} | --file file
```

For a VirtualBox hypervisor host object, use the following syntax:

```
visulox-portal object new_host {
--name obj
--address address
--vbox
[ --description text ]
[ --available true|false ]
[ --auth trytta|nevertrytta|default ]
[ --vmsubnet network-address/mask ]
[ --vboxgroups group... ]
[ --vmnames vm-name... ]
[ --vmostypes os-type... ]
[ --maxcount count ]
[ --userassign spec ]
[ --sgdpermittedauthtypes types ]
} | --file file
```

## Description

Available options for this command.

--name	The names of objects you want to add assigned applications links <b>for</b> .
--address	Network address of the application server. For hypervisor hosts, enter the web services URL.
--dynamic	Create a dynamic application server.
--ovm	Create an Oracle VM hypervisor host.

<code>--vbox</code>	Create a VirtualBox hypervisor host.
<code>--description</code>	A text description of the object.
<code>--ntdomain</code>	The Windows domain used <b>for</b> application server authentication.
<code>--available</code>	Specifies whether applications can run on <b>this</b> application server.
<code>--auth</code>	Specifies the policy <b>for</b> authenticating users on the application server, <b>if</b> no password is already cached <b>for</b> that server.
<code>--location</code>	String describing the location of the application server. Used <b>for</b> load balancing.
<code>--hostlocale</code>	Default language setting <b>for</b> the application server.
<code>--vsbclass</code>	Fully qualified <b>class</b> name <b>for</b> the virtual server broker (VSB). Dynamic application servers only.
<code>--vsbparams</code>	Parameters passed to the VSB. Dynamic application servers only.
<code>--vmsubnet</code>	Connect only to VMs which use an IP address on the specified subnet. Oracle VM hypervisor hosts and VirtualBox hypervisor hosts only.
<code>--ovmtags</code>	Tags used <b>for</b> VM selection criteria. Oracle VM hypervisor hosts only.
<code>--ovmpools</code>	Server pool names used <b>for</b> VM selection criteria. Oracle VM hypervisor hosts only.
<code>--ovmservers</code>	Oracle VM Server names used <b>for</b> VM selection criteria. Oracle VM hypervisor hosts only.
<code>--vmnames</code>	VM names used <b>for</b> VM selection criteria. Oracle VM hypervisor hosts and VirtualBox hypervisor hosts only.
<code>--vmotypes</code>	Operating system (OS) types used <b>for</b> VM selection criteria. Oracle VM hypervisor hosts and VirtualBox hypervisor hosts only.
<code>--vboxgroups</code>	Oracle VM VirtualBox groups used <b>for</b> VM selection criteria. VirtualBox hypervisor hosts only.
<code>--maxcount</code>	Maximum number of application sessions that can be run concurrently on the application server.
<code>--userassign</code>	Specifies the users that can run applications on the application server.
<code>--sgdpermittedauthtypes</code>	Specifies the authentication methods which are allowed <b>for this</b> application server.
<code>--file</code>	A file containing a batch of commands to add assigned applications links.

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

## Examples

The following example creates a new application server object with common name paris, belonging to the organizational unit object Finance, which must already exist.

```
visulox-portal object new_host --name "o=appservers/ou=Finance/cn=paris" \
```

```
--address paris.example.com --auth default --location Europe-north
```

The following example creates a new dynamic application server object MyBroker that uses the Userdefined VISULOX Portal broker.

```
visulox-portal object new_host --dynamic --name "o=appservers/cn=MyBroker" \  
--vsbclass com.sun.sgd.vsbim.UserDefinedSGDBroker
```

The following example creates a new dynamic application server object MyVDIBroker that uses the VDI broker. A list of preferredhosts is configured for the broker.

```
visulox-portal object new_host --dynamic --name "o=appservers/cn=MyVDIBroker" \  
--vsbclass com.oracle.sgd.vsbim.OracleVDIVirtualServerBroker \  
--vsbparams "preferredhosts=\"https://vdihost1.com:1802/client,https://vdihost2.com:1802/client,https://vdihost3.com:1802/  
client\""
```

The following example creates a new Oracle VM hypervisor object ovm1 that connects to the Oracle VM Manager host [ovm-mgr.example.com](https://ovm-mgr.example.com) on TCP port 7002. Only VMs which have a tag of marketing or sales are used by VISULOX Portal.

```
visulox-portal object new_host --ovm --name "o=appservers/cn=ovm1" \  
--address "https://ovm-mgr.example.com:7002/ovm/core/wsapi/rest" --ovmtags "marketing,sales"
```

The following example creates a new Oracle VM hypervisor object ovm1 that connects to the Oracle VM Manager host [ovm-mgr.example.com](https://ovm-mgr.example.com) on TCP port 7002. Only VMs which have an IP address on the specified subnet are used by VISULOX Portal.

```
visulox-portal object new_host --ovm --name "o=appservers/cn=ovm1" \  
--address "https://ovm-mgr.example.com:7002/ovm/core/wsapi/rest" --vmsubnet 192.0.2.0/24
```

The following example creates a new VirtualBox hypervisor object vbox1 that connects to the Oracle VM VirtualBox host [vbox.example.com](https://vbox.example.com). Only VMs which are members of the Oracle VM VirtualBox groups support or sales are used by VISULOX Portal.

```
visulox-portal object new_host --vbox --name "o=appservers/cn=vbox1" \  
--address "https://vbox.example.com:18083" --vboxgroups "support,sales"
```

The following example creates three application server objects using a batch script defined as a “here-document”. Alternatively, you can store the batch script in a file, and reference it using `--file filename`.

```
visulox-portal object new_host --file - <<EOF  
--name "o=appservers/ou=Finance/cn=paris"  
--address paris.example.com  
--name "o=appservers/cn=brussels"  
--address brussels.example.com  
--name "o=appservers/ou=IT/cn=london"  
--address london.example.com  
EOF
```

#### 4.4.15 visulox-portal object new\_org

##### Syntax

Creates one or more organization objects.

```
visulox-portal object new_org {  
--name obj  
[ --description text ]  
[ --conntype type_spec... ]
```

```

[ --cdm drive_spec... ]
[ --userprintingconfig true|false ]
[ --mapprinters 2|1|0 ]
[ --pdfenabled 1|0 ]
[ --pdfviewerenabled 1|0 ]
[ --pdfdriver driver_name ]
[ --pdfisdefault 1|0 ]
[ --pdfviewerisdefault 1|0 ]
[ --links obj... ]
[ --editprofile 2|1|0 ]
[ --clipboard 2|1|0 ]
[ --serialport 2|1|0 ]
} | --file file

```

## Description

Available options for this command.

<code>--name</code>	The name of the organization object in the VISULOX Portal datastore.
<code>--description</code>	A text description of the object.
<code>--conntype</code>	The connections that are allowed between the client device and the VISULOX Portal server.
<code>--userprintingconfig</code>	Enables user-specific printing configuration.
<code>--mapprinters</code>	The client printers users can print to when printing from Windows applications.
<code>--pdfenabled</code>	Enables users to print using the VISULOX Portal “Universal PDF Printer” printer when printing from Windows applications.
<code>--pdfviewerenabled</code>	Enables users to print using the VISULOX Portal “Universal PDF Viewer” printer when printing from Windows applications.
<code>--pdfdriver</code>	The printer driver to use <b>for</b> VISULOX Portal PDFprinting when printing from Windows applications.
<code>--pdfisdefault</code>	Sets the VISULOX Portal “Universal PDF Printer” printer as the client's <b>default</b> printer when printing from Windows applications.
<code>--pdfviewerisdefault</code>	Sets the VISULOX Portal “Universal PDF Viewer” printer as the client's <b>default</b> printer when printing from Windows applications.
<code>--links</code>	Defines assigned applications links.

<code>--editprofile</code>	Whether users can create and edit profiles <b>for</b> use with the Native Client.
<code>--clipboard</code>	Whether users can use copy and paste in Windows or X application sessions.
<code>--serialport</code>	Whether users can access the serial ports on a client device from a Windows application.
<code>--file</code>	Batch file used to create multiple objects within the organizational hierarchy.

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new organization object with name Example.

Connections for all users in the organization are secure (SSL-based) unless the OU or user profile objects are configured to give a different type of connection.

```
visulox-portal object new_org --name "o=Example" --conntype '*:*:SSL'
```

The following example creates two organization objects using a batch script defined as a “here-document”.

You can alternatively store the batch script in a file, and reference it using `--file filename`.

```
visulox-portal object new_org --file - <<EOF
--name "o=Example"
--name "o=Example Services"
EOF
```

### 4.4.16 visulox-portal object new\_orgunit

Creates one or more organizational unit (OU) objects

## Syntax

```
visulox-portal object new_orgunit {  
  --name obj  
  [ --description text ]  
  [ --inherit true|false ]  
  [ --conntype type_spec... ]  
  [ --cdm drive_spec... ]  
  [ --userprintingconfig 1|0 ]  
  [ --mapprinters 2|1|0 ]  
  [ --pdfenabled 1|0 ]  
  [ --pdfviewerenabled 1|0 ]  
  [ --pdfdriver driver_name ]  
  [ --pdfisdefault 1|0 ]  
  [ --pdfviewerisdefault 1|0 ]  
  [ --links obj... ]  
  [ --editprofile 2|1|0 ]  
  [ --clipboard 2|1|0 ]  
  [ --serialport 2|1|0 ]  
} | --file file
```

## Description

The following table shows the available options for this command.

<code>--name</code>	The name of the organizational unit object in the VISULOX Portal datastore.
<code>--description</code>	A text description of the object.
<code>--inherit</code>	Whether the assigned applications <b>for</b> the object also includes the assigned applications <b>for</b> the object's parent.
<code>--conntype</code>	The connections that are allowed between the client device and the VISULOX Porion servers.
<code>--userprintingconfig</code>	Enables user-specific printing configuration.

<code>--mapprinters</code>	The client printers users can print to when printing from Windows applications.
<code>--pdfenabled</code>	Enables users to print using the VISULOX Portal “Universal PDF Printer” printer when printing from Windows applications.
<code>--pdfviewerenabled</code>	Enables users to print using the VISULOX Portal “Universal PDF Viewer” printer when printing from Windows applications.
<code>--pdfdriver</code>	The printer driver to use <b>for</b> VISULOX Portal PDF printing when printing from Windows applications.
<code>--pdfisdefault</code>	Sets the VISULOX Portal “Universal PDF Printer” printer as the client's <b>default</b> printer when printing from Windows applications.
<code>--pdfviewerisdefault</code>	Sets the VISULOX Portal “Universal PDF Viewer” printer as the client's <b>default</b> printer when printing from Windows applications.
<code>--links</code>	Defines the assigned applications <b>for</b> an object.
<code>--editprofile</code>	Whether users can create and edit profiles <b>for</b> use with the Native Client.
<code>--clipboard</code>	Whether users can use copy and paste in Windows or X application sessions.
<code>--serialport</code>	Whether users can access the serial ports on a client device from a Windows application.
<code>--file</code>	Batch file used to create multiple objects within the organizational hierarchy.

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new OU object with the name IT, belonging to the organization object Example, which must already exist. This OU inherits assigned applications from its parent, the organization object. Connections for all users in the OU are secure (SSL-based) unless their user profile objects are configured to give a different type of connection.

```
visulox-portal object new_orgunit --name "o=Example/ou=IT" --inherit true --conntype '*:*:SSL'
```

The following example creates three OU objects using a batch script defined as a “here-document”. The OU Administration belongs to the OU Finance, just created. You can alternatively store the batch script in a file, and reference it using `--file filename`.

```
visulox-portal object new_orgunit --file - <<EOF
--name "o=Example/ou=IT"
--name "o=Example/ou=Finance"
```

```
--name "o=Example/ou=Finance/ou=Administration"  
EOF
```

#### 4.4.17 visulox-portal object new\_person

Creates one or more user profile objects.

##### Syntax

```
visulox-portal object new_person {  
  --name obj  
  --surname surname  
  [ --description text ]  
  [ --user user ]  
  [ --email name@domain ]  
  [ --ntdomain dom ]  
  [ --inherit true|false ]  
  [ --shared true|false ]  
  [ --enabled true|false ]  
  [ --conntype type_spec... ]  
  [ --cdm drive_spec... ]  
  [ --keymap keymap ]  
  [ --bandwidth limit ]  
  [ --links obj... ]  
  [ --userprintingconfig 1|0 ]  
  [ --mapprinters 2|1|0 ]  
  [ --pdfenabled 1|0 ]  
  [ --pdfviewerenabled 1|0 ]  
  [ --pdfdriver driver_name ]  
  [ --pdfisdefault 1|0 ]
```

```
[ --pdfviewerisdefault 1|0 ]
[ --editprofile 2|1|0 ]
[ --clipboard 2|1|0 ]
[ --serialport 2|1|0 ]
} | --file file
```

## Description

Available options for this command.

<code>--name</code>	The common name of the object in the VISULOX Portal datastore.
<code>--surname</code>	The surname, or family name, <b>for</b> the user profile.
<code>--description</code>	A text description of the object.
<code>--user</code>	The user name <b>for</b> the user profile. This is typically their UNIX system user name.
<code>--email</code>	The email address <b>for</b> the user profile.
<code>--ntdomain</code>	The Windows domain used <b>for</b> application server authentication.
<code>--inherit</code>	Whether the assigned applications <b>for</b> the object also includes the assigned applications <b>for</b> the object's parent.
<code>--shared</code>	Whether the user profile object is used by a single user, or can be shared by multiple users in the form of a “guest” account.
<code>--enabled</code>	Whether someone can log in using <b>this</b> user profile object.
<code>--conntype</code>	Defines the connections that are allowed between the client device and the VISULOX Portal server.
<code>--bandwidth</code>	The maximum bandwidth <b>this</b> person can use <b>for</b> applications.
<code>--links</code>	Defines the assigned applications <b>for</b> an object.
<code>--userprintingconfig</code>	Enables user-specific printing configuration.
<code>--mapprinters</code>	The client printers users can print to when printing from Windows applications.
<code>--pdfenabled</code>	Enables users to print using the VISULOX Portal “Universal PDF Printer” printer when printing from Windows applications.
<code>--pdfviewerenabled</code>	Enables users to print using the VISULOX Portal “Universal PDF Viewer” printer when printing from Windows applications.
<code>--pdfdriver</code>	The printer driver to use <b>for</b> VISULOX Portal PDF printing when printing from Windows applications.
<code>--pdfisdefault</code>	Sets the VISULOX Portal “Universal PDF Printer” printer as the client's <b>default</b> printer when printing from Windows applications.

```
--pdfviewerisdefault  Sets the VISULOX Portal “Universal PDF Viewer” printer as the client's default printer when printing from
Windows applications.
--editprofile          Whether users can create and edit profiles for use with the VISULOX Portal Client.
--clipboard            Whether users can use copy and paste in X or Windows application sessions.
--serialport          Whether users can access the serial ports on a client device from a Windows application.
--file                 Batch file used to create multiple objects within the organizational hierarchy.
```

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new user profile object for Indigo Jones. Indigo inherits assigned applications from the organization object.

```
visulox-portal object new_person --name "o=Example/cn=Indigo Jones" \  
--surname Jones --user indigo --email indigo@example.com --inherit true
```

The following example creates three user profile objects using a batch script defined as a “here-document”. You can alternatively store the batch script in a file, and reference it using `--file filename`.

```
visulox-portal object new_person --file - <<EOF  
--name "o=Example/cn=Indigo Jones" --surname Jones  
--name "o=Example/ou=IT/cn=Bill Orange" --surname Orange  
--name "o=Example/ou=Finance/cn=Mulan Rouge" --surname Rouge  
EOF
```

### 4.4.18 visulox-portal object new\_windowsapp

Creates one or more Windows application objects.

## Syntax

```
visulox-portal object new_windowsapp {
--name obj
--width pixels
--height pixels
[ --description text ]
[ --winproto wts|none ]
[ --ntdomain dom ]
[ --app pathname ]
[ --args args ]
[ --appserv obj... ]
[ --workingdir dir ]
[ --resumable never|session|always ]
[ --displayusing independent|kiosk|seamless ]
[ --maxinstances 0|instances ]
[ --maximize true|false ]
[ --scalable true|false ]
[ --depth 8|16|24|32 ]
[ --icon icon_name ]
[ --hints hint...]
[ --compression automatic|on|off ]
[ --execution automatic|inorder|optimized ]
[ --interlaced automatic|on|off ]
[ --enhancedgraphics 1|0 ]
[ --delayed true|false ]
[ --login script ]
[ --protoargs args ]
[ --resumetimeout mins ]
[ --middlemouse ms ]
[ --dpi monitordpi ]
[ --loadbal default|cpu|memory|sessions ]
```

```
[ --ldapusers user_dn... ]
[ --ldapgroups group_dn... ]
[ --ldapsearch search_string... ]
[ --clipboardlevel level ]
[ --windowclose suspendsession|endsession ]
[ --cdm drive_spec... ]
[ --appprintingconfig 1|0 ]
[ --mapprinters 2|1|0 ]
[ --pdfenabled 1|0 ]
[ --pdfviewerenabled 1|0 ]
[ --pdfdriver driver_name ]
[ --pdfisdefault 1|0 ]
[ --pdfviewerisdefault 1|0 ]
[ --allowkioskescape true|false ]
[ --swmopts true|false ]
[ --console 1|0 ]
[ --remotewindowkeys true|false ]
[ --disablewallpaper 1|0 ]
[ --disablefullwindowdrag 1|0 ]
[ --disablemenuanimations 1|0 ]
[ --disabletheming 1|0 ]
[ --disablecursorshadow 1|0 ]
[ --disablecursorsettings 1|0 ]
[ --enablefontsmoothing 1|0 ]
[ --noprintprefs 1|0 ]
[ --remoteaudio 1|0 ]
[ --enhancednetworksecurity 1|0 ]
[ --ssoauth 2|1|0 ]
} | --file file
```

## Description

The following table shows the available options for this command.

<code>--name</code>	The common name of the object in the VISULOX Portal datastore.
<code>--width</code>	The width of the application, in pixels.
<code>--height</code>	The height of the application, in pixels.
<code>--description</code>	A text description of the object.
<code>--winproto</code>	Whether to run the Windows application from an application server using Remote Desktop Protocol.
<code>--ntdomain</code>	The Windows domain to use <b>for</b> the application server authentication process.
<code>--app</code>	Full path name of the application.
<code>--args</code>	The command-line arguments to use when starting the application.
<code>--appserv</code>	The application servers that can run the application.
<code>--workingdir</code>	Working directory to be used by the application.
<code>--resumable</code>	Resumability behavior <b>for</b> the application.
<code>--displayusing</code>	How the application is displayed to the user.
<code>--maxinstances</code>	The maximum number of instances of the application a user can run simultaneously.
<code>--maximize</code>	The initial size of the application.
<code>--scalable</code>	Scale the application to fit the window in which it is displayed.
<code>--depth</code>	Color depth <b>for</b> the application.
<code>--icon</code>	Workspace icon <b>for</b> the application.
<code>--hints</code>	String containing additional namevalue data <b>for</b> the application.
<code>--compression</code>	Whether the AIP protocol compresses commands <b>for</b> transmission.
<code>--execution</code>	Whether the AIP protocol always executes commands in order, or optimizes commands <b>for</b> performance reasons.
<code>--interlaced</code>	Enables interlaced image transmission.
<code>--enhancedgraphics</code>	Enables enhanced graphics <b>for</b> the application's display.
<code>--delayed</code>	Enables delayed updates of the application's display.
<code>--login</code>	The login script used to start the application.
<code>--protoargs</code>	Command-line arguments used <b>for</b> the VISULOX Portal Remote Desktop Client.
<code>--resumetimeout</code>	Number of minutes the application is resumable <b>for</b> .
<code>--middlemouse</code>	Timeout <b>for</b> emulating a middle mouse button click using a twobutton mouse.
<code>--dpi</code>	Monitor resolution that VISULOX Portal reports to X applications.
<code>--loadbal</code>	Load balancing algorithm to use.
<code>--ldapusers</code>	Assigns the application to the specified LDAP users.
<code>--ldapgroups</code>	Assigns the application to the specified LDAP groups.
<code>--ldapsearch</code>	Assigns the application to the users that match the LDAP search criteria.

<code>--clipboardlevel</code>	Clipboard security level <b>for</b> the application.
<code>--windowclose</code>	Effect on application session of closing the main application window.
<code>--appprintingconfig</code>	Enables application-specific printing configuration.
<code>--mapprinters</code>	The client printers users can print to when printing from the application.
<code>--pdfenabled</code>	Enables users to print using the VISULOX Portal “Universal PDF Printer” printer when printing from the application.
<code>--pdfviewerenabled</code>	Enables users to print using the VISULOX Portal “Universal PDF Viewer” printer when printing from the application.
<code>--pdfdriver</code>	The printer driver to use <b>for</b> VISULOX Portal PDF printing when printing from the application.
<code>--pdfisdefault</code>	Sets the VISULOX Portal “Universal PDF Printer” printer as the client's <b>default</b> printer when printing from the application.
<code>--pdfviewerisdefault</code>	Sets the VISULOX Portal “Universal PDF Viewer” printer as the client's <b>default</b> printer when printing from the application.
<code>--allowkioskescape</code>	Enables a pull-down header <b>for</b> kiosk mode applications.
<code>--swmopts</code>	Enables local window hierarchy <b>for</b> applications displayed in seamless windows mode. Needed <b>for</b> compatibility with some Borland applications.
<code>--console</code>	Starts the application in console mode, also called remote administration mode.
<code>--remotewindowkeys</code>	Sends window management key strokes to the remote session.
<code>--disablewallpaper</code>	Disables background wallpaper. This can improve performance.
<code>--disablefullwindowdrag</code>	Disables the option to show the contents of a window when it is moved. This can improve performance.
<code>--disablemenuanimations</code>	Disables transition effects <b>for</b> menus and tooltips. This can improve performance.
<code>--disabletheming</code>	Disables themes <b>for</b> the application. This can improve performance.
<code>--disablecursorshadow</code>	Disables the mouse pointer shadow. This can improve performance.
<code>--disablecursorsettings</code>	Disables mouse pointer schemes and customizations. This can improve performance.
<code>--enablefontsmoothing</code>	Enables font smoothing <b>for</b> text in the application. This can improve text readability, but can affect performance.
<code>--noprintprefs</code>	Disables caching of printer preferences, such as paper size and page orientation.
<code>--remoteaudio</code>	Leaves audio at the remote application server.
<code>--enhancednetworksecurity</code>	Uses enhanced security, such as Transport Layer Security (TLS) or Network Level Authentication (NLA) using CredSSP.
<code>--ssoauth</code>	Uses single sign-on authentication <b>for</b> the application.
<code>--file</code>	Batch file used to create multiple objects within the organizational hierarchy.

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new Windows application object for the application Write-o-Win. The application runs on the application server rome.

```
visulox-portal object new_windowsapp --name "o=applications/cn=Write-o-Win" \  
--width 1000 --height 800 --app c:\\programs\\apps\\write.exe \  
--appserv "o=appservers/ou=Sales/cn=rome"
```

### 4.4.19 visulox-portal object new\_xapp

Creates one or more X application objects.

#### Syntax

```
visulox-portal object new_xapp {  
--name obj  
--width pixels  
--height pixels  
[ --description text ]  
[ --app pathname ]  
[ --args args ]  
[ --appserv obj... ]  
[ --method telnet|ssh ]  
[ --resumable never|session|always ]  
[ --endswhen lastclient|windowmanager|windowmanageralone|nowindows|loginscript|loginscriptnowindows ]  
[ --maxinstances 0|instances ]  
[ --displayusing clientwm|independent|kiosk ]  
[ --variablerootsize true|false ]  
[ --maximize true|false ]
```

```
[ --scalable true|false ]
[ --depth 8|16|24|16/8|24/8|8/16|8/24 ]
[ --icon icon_name ]
[ --hints hint... ]
[ --clipboardlevel level ]
[ --roottype default|custom ]
[ --rootcolor color ]
[ --compression automatic|on|off ]
[ --execution automatic|inorder|optimized ]
[ --quality automatic|best|24|21|18|16|15|12|9|6 ]
[ --interlaced automatic|on|off ]
[ --enhancedgraphics 1|0 ]
[ --delayed true|false ]
[ --ldapusers user_dn... ]
[ --ldapgroups group_dn... ]
[ --ldapsearch search_string... ]
[ --loadbal default|cpu|memory|sessions ]
[ --env setting... ]
[ --login script ]
[ --winmgr command... ]
[ --resumetimeout mins ]
[ --middlemouse ms ]
[ --force3button true|false ]
[ --windowclose notifyapp|killapp|suspendsession|endsession ]
[ --dpi monitordpi ]
[ --keepopen true|false ]
[ --share true|false ]
[ --securityextension true|false ]
[ --ssharguments args ]
[ --unixaudiopreload true|false ]
[ --remotewindowkeys true|false ]
[ --allowkioskescape true|false ]
[ --allowsshdowngrade true|false ]
[ --ssoauth 2|1|0 ]
```

```
} | --file file
```

## Description

Available options for this command.

<code>--name</code>	The common name of the object in the VISULOX Portal datastore.
<code>--width</code>	The width of the application, in pixels.
<code>--height</code>	The height of the application, in pixels.
<code>--description</code>	A text description of the object.
<code>--app</code>	Full path name of the application.
<code>--args</code>	The command-line arguments to use when starting the application.
<code>--appserv</code>	The application servers that can run the application.
<code>--method</code>	The mechanism used by the VISULOX Portal server to access the application server and start the application.
<code>--resumable</code>	Resumability behavior <b>for</b> the application.
<code>--endswhen</code>	When the application session ends.
<code>--maxinstances</code>	The maximum number of instances of the application a user can run simultaneously.
<code>--displayusing</code>	How the application is displayed to the user.
<code>--variablerootsize</code>	Resize the root window to match the size of the user's screen.
<code>--maximize</code>	The initial size of the application.
<code>--scalable</code>	Scale the application to fit the window in which it is displayed.
<code>--depth</code>	Color depth <b>for</b> the application
<code>--icon</code>	Workspace icon <b>for</b> the application.
<code>--hints</code>	String containing additional name-value data <b>for</b> the application.
<code>--clipboardlevel</code>	Clipboard security level <b>for</b> the application.
<code>--roottype</code>	Appearance of the root window.
<code>--rootcolor</code>	Color of the root window
<code>--compression</code>	Whether the AIP protocol compresses commands <b>for</b> transmission.
<code>--execution</code>	Whether the AIP protocol always executes commands in order, or optimizes commands <b>for</b> performance reasons.
<code>--quality</code>	The effective color depth displayed on client devices.
<code>--interlaced</code>	Enables interlaced image transmission.
<code>--enhancedgraphics</code>	Enables enhanced graphics <b>for</b> the application's display.

<code>--delayed</code>	Enables delayed updates of the application's display.
<code>--ldapusers</code>	Assigns the application to the specified LDAP users.
<code>--ldapgroups</code>	Assigns the application to the specified LDAP groups.
<code>--ldapsearch</code>	Assigns the application to the users that match the LDAP search criteria.
<code>--loadbal</code>	Load balancing algorithm to use.
<code>--env</code>	Environment variable settings needed to run the application.
<code>--login</code>	The login script used to start the application.
<code>--winmgr</code>	The Window Manager to use <b>for</b> the application.
<code>--resumetimeout</code>	Number of minutes the application is resumable <b>for</b> .
<code>--middlemouse</code>	Timeout <b>for</b> emulating a middle mouse button click using a two-button mouse.
<code>--force3button</code>	Specifies that the application only supports a 3-button mouse.
<code>--windowclose</code>	Effect on application session of closing the main application window.
<code>--dpi</code>	Monitor resolution that VISULOX Portal reports to X applications.
<code>--keepopen</code>	Keep open the connection used to start the application.
<code>--share</code>	Enables resource sharing <b>for</b> similar application sessions.
<code>--securityextension</code>	Enables the X Security Extension <b>for</b> the application.
<code>--ssharguments</code>	Command-line arguments <b>for</b> the ssh client.
<code>--unixaudiopreload</code>	Enables the VISULOX Portal audio redirection library.
<code>--remotewindowkeys</code>	Sends window management key strokes to the remote session.
<code>--allowkioskescape</code>	Enables a pull-down header <b>for</b> kiosk mode applications.
<code>--allowsshdowngrade</code>	Enables VISULOX Portal to <b>try</b> an X11 connection instead of SSH, when X11 forwarding is not configured or working.
<code>--ssoauth</code>	Uses single sign-on authentication <b>for</b> the application.
<code>--file</code>	Batch file used to create multiple objects within the organizational hierarchy.

To batch-create multiple objects, use the `--file` option. Use the other options to create a single object.

## Examples

The following example creates a new X application object for the application XFinance. The application can be run on the application servers paris, bonn, or lisbon. Application server load balancing decides which one to use.

```
visulox-portal object new_xapp --name "o=applications/ou=Finance/cn=XFinance" \
--width 1000 --height 800 --app /usr/local/bin/xfinance \
```

```
--appserv "o=appservers/ou=Finance/cn=paris" \  
"o=appservers/ou=Finance/cn=bonn" "o=appservers/cn=lisbon"
```

#### 4.4.20 visulox-portal object remove\_host

Removes application servers from the list of those that can run an application, for application server load balancing.

##### Syntax

```
visulox-portal object remove_host { --name obj... --host hobj...} | --file file
```

##### Description

Available options for this command.

--name	Specifies the names of application objects you want to configure load balancing <b>for</b> .
--host	Specifies the names of application server objects you want to remove from the load balancing pool.
--file	Specifies a file containing a batch of commands to configure application server load balancing.

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

##### Examples

The following example removes the application server rome from the load balancing pool for the application Slide-o-Win.

```
visulox-portal object remove_host --name "o=applications/cn=Slide-o-Win" \  
--host "o=appservers/ou=Sales/cn=rome"
```

The following example removes the group WinHosts from the load balancing pool for the applications Write-o-Win and Slide-o-Win. Load balancing is no longer performed across all the application servers in WinHosts.

```
visulox-portal object remove_host --name "o=applications/cn=Write-o-Win" \  
"o=applications/cn=Slide-o-Win" --host "o=appservers/cn=WinHosts"
```

#### 4.4.21 visulox-portal object remove\_link

Removes assigned applications links for an object.

##### Syntax

```
visulox-portal object remove_link { --name obj... --link lobj... } | --file file
```

##### Description

Available options for this command.

<code>--name</code>	Specifies the names of objects you want to remove links <b>for</b> .
<code>--link</code>	Specifies the names of objects you want to remove links <b>for</b> .
<code>--file</code>	Specifies a file containing a batch of commands to remove links <b>for</b> .

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

## Examples

The following example removes the Write-o-Win application from the assigned applications for Violet Carson.

```
visulox-portal object remove_link --name "o=Example/ou=Sales/cn=Violet Carson" --link "o=applications/cn=Write-o-Win"
```

The following example removes the group Applications from the assigned applications of the organizational units Sales and Marketing. Everyone who inherits assigned applications from one of these OUs no longer sees all the applications in their assigned applications. For example, if they belong to that OU and is selected for their user profile object. However, they may still see an application if it is inherited from elsewhere.

```
visulox-portal object remove_link --name "o=Example/ou=Sales" \  
"o=Example/ou=Marketing" --link "o=applications/cn=Applications"
```

### 4.4.22 visulox-portal object remove\_mapping

Removes type-application mappings for a dynamic application object.

#### Syntax

```
visulox-portal object remove_mapping [--name obj --mappingtype [type]] | --file file
```

#### Description

Available options for this command.

<code>--name</code>	The name of the dynamic application object.
---------------------	---

```
--mappingtype  Type of mapping to be removed.  
--file         A file containing a batch of commands to remove mappings.
```

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

## Examples

The following example removes a mapping for the windows type from a dynamic application object with common name winApp.

```
visulox-portal object remove_mapping --name "o=applications/cn=winApp" --mappingtype windows
```

The following example removes a mapping for the solaris type from a dynamic application object named desktopApp.

```
visulox-portal object remove_mapping --name "o=applications/cn=desktopApp" --mappingtype solaris
```

### 4.4.23 visulox-portal object remove\_member

Removes objects from groups.

## Syntax

```
visulox-portal object remove_member { --name obj... --member mobj... } | --file file
```

## Description

Available options for this command.

```
--name      Specifies the names of group objects you want to remove members from.
--member    Specifies the names of objects you want to remove from the groups.
--file      Specifies a file containing a batch of commands to remove group members.
```

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

## Examples

The following example removes the Write-o-Win application from the group Applications.

```
visulox-portal object remove_member --name "o=applications/cn=Applications" --member "o=applications/cn=Write-o-Win"
```

The following example removes the three application server objects rome, brussels, and berlin from the group WinHosts.

```
visulox-portal object remove_member --name "o=appservers/cn=WinHosts" \  
--member "o=appservers/ou=Sales/cn=rome" "o=appservers/cn=brussels" \  
"o=appservers/ou=Marketing/cn=berlin"
```

### 4.4.24 visulox-portal object rename

Renames or moves an object in the organizational hierarchy.

## Syntax

```
visulox-portal object rename { --name obj... --newname newobj...} | --file file
```

## Description

The following table shows the available options for this command.

--name	Specifies the name of the object you want to rename or move.
--newname	Specifies the <b>new</b> name of the object.
--file	Specifies a file containing a batch of commands to rename or move objects.

**i** Make sure you quote any object names containing spaces, for example, "o=Example Organization".

## Examples

The following example renames the user profile object for Elizabeth Blue to Liz Blue.

```
visulox-portal object rename --name "o=Example/ou=Sales/cn=Elizabeth Blue" \  
--newname "o=Example/ou=Sales/cn=Liz Blue"
```

The following example moves Ginger Butcher between the organizational units IT and Sales.

```
visulox-portal object rename --name "o=Example/ou=IT/cn=Ginger Butcher" \  
--newname "o=Example/ou=Sales/cn=Ginger Butcher"
```

## 4.4.25 visulox-portal object script

Runs a batch script of visulox-portal object commands, or enables commands to be run interactively.

### Syntax

```
visulox-portal object script
```

### Description

The batch script consists of standard visulox-portal object commands, one per line, *without* the visulox-portal object prefix. For example, use edit rather than visulox-portal object edit.

The batch script can use a back slash (\) to break commands across multiple lines. Lines beginning with a hash (#) are treated as comments and ignored.

If you need to include quotes (") or a backslash (\) character in any of the values for the commands, you must backslash protect them. For example, to use "c:\\Program Files\" as a value for the --args option, type the following: --args "\"c:\\Program Files\""

The command reads from standard input. For example, you can use a "here-document" to run a batch script:

```
visulox-portal object script <<EOF
commands
EOF
```

If standard input is empty, you can run visulox-portal object commands interactively.


### Examples

The following example adds the group Applications to the organizational units Sales and Marketing, and sets the Sales OU's attribute to false.

```
visulox-portal object script <<EOF
add_link
--name "o=Example/ou=Sales"
"o=Example/ou=Marketing"
--link "o=Example/cn=Applications"
edit
--name "o=Example/ou=Sales" --inherit false
EOF
```

## 4.5 VISULOX-GATEWAY Command

```
visulox-gateway <command> [<command-specific args>]
```

 During installation **/usr/sbin/visulox-gateway** is created, which makes it possible to execute the VISULOX GATEWAY Command without using the whole path.

### 4.5.1 Available parameters

Command	Description
start	Start VISULOX GATEWAY
stop	Stop VISULOX GATEWAY
restart	Restart VISULOX GATEWAY
config	Configuration options: create, list, edit, enable, disable

Command	Description
server	Server options: add, add-array, remove, list, list-array
status	Show VISULOX GATEWAY status
version	Show VISULOX GATEWAY version
sslcert	Export, print sslcert
sslkey	Import, export sslkey
cert	Export the VISULOX GATEWAY certificate
clientcert	Import, list, remove clientcert
key	Import private key and its corresponding certificate
patch	Add, remove, list VISULOX GATEWAY patches
connection	List connections
support	VISULOX Gateway Support Report



With **visulox-gateway <subcommand> --help** the detailed options for a command can be displayed.  
 If more parameters are needed for a command, the available options are always displayed by entering the basic command.

## 4.5.2 Usage

The following examples show the usage of the VISULOX-GATEWAY Command:

### Show VISULOX GATEWAY status

```
visulox-gateway status
```

### Show version information

```
visulox-gateway version
```

### List VISULOX PORTAL Servers / certificates

```
visulox-gateway server list
```

### Show VISULOX GATEWAY configuration

```
visulox-gateway config list
```

### Add the VISULOX Portal Array on external Gateway

```
visulox-gateway server add-array --name osgd --serverurl <https://fqdn of the primary portal server>
```

## 4.6 Integrity-Check

The Integrity-Check is started automatically during installation of VISULOX to make sure, that all requirements are met for a properly running system. However Integrity-Check can also be used in an already running environment for diagnose purpose.

**Integrity-Check can be started via the visulox command:**

```
visulox integrity
```

In the quiet mode no shell output and no log entries in **/tmp/visulox-integrity.log** are written.

Only the Integrity-Check exit code will be returned:

```
visulox integrity -quiet
```

### 4.6.1 Available Integrity-Check commands

Command	Description
-sw	Check of online software status
-vlx	Check the VLX Services and cluster ports

<b>Command</b>	<b>Description</b>
-sys	Check the system environment
-lib	Check for missing libs
-cmd	Check command for missing libraries
-disk	Check disk
-users	Check VISULOX transit users
-portal	Check the VISULOX PORTAL Service
-cert	Check certificates within VISULOX and VISULOX PORTAL
-store	Check store
-recorder	Check recorder
-datasources	Check datasources
-assignments	Check datastore assignments and dynamic applications
-license	Check license

Command	Description
-policies	Check policies (VISULOX must be online)
-index	Check index
-scripts	Check scripts
-x11forward	Check x11forward
-gate	Check gate config
-mail	Check mail configuration

#### 4.6.2 General commands

Command	Description
-format <value>	Format of output (text,xml,csv,json,tcl) <text>
-verbose	More messages on stdout
--	Forcibly stop option processing

Command	Description
-help	Print this message
-?	Print this message

### 4.6.3 Usage

```
visulox integrity

Please wait ....
Integrity-Check: amitego engineering - in house license / beta2-3.1.1 / 2016-07-12 12:46:32 UTC
-----
| option | cat | info | returnCode |
-----
| -license | check | Evaluation | WARNING(2) |
| -sys | Script /opt/visulox/tools/filecheck.sh | not configured | WARNING(2) |
| -sys | Script /opt/visulox/tools/event.sh | not configured | WARNING(2) |
| -portal | 5.60 Warnings | see logfile | WARNING(2) |
-----

ExitCode: WARNING
Check the warnings. For more information see /tmp/visulox-integrity.log
```

**i** Only warnings and errors are displayed by default. All Integrity checks can be shown with the **-verbose** parameter.

## visulox integrity -portal

option	cat	info	returnCode
-portal	core	PORTAL 5.60	SUCCESS(0)
-portal	connect	yes	SUCCESS(0)
-portal	webtop	ok	SUCCESS(0)
-portal	var	security-xsecurity ok	SUCCESS(0)
-portal	var	xpe-maxsessions ok	SUCCESS(0)
-portal	var	xpe-maxusers ok	SUCCESS(0)
-portal	role	administrator is root	WARNING(2)
-portal	array	P: mp-vlx32-ol7.tbsol.de	SUCCESS(0)
-portal	security-gateway	mp-vlx32-ol7.tbsol.de is good	SUCCESS(0)

## visulox integrity -cert

option	cat	info	returnCode
-cert	SSL-CERT	issuer = /C=de/ST=de/O=amitego/CN=test.tbsol.de	SUCCESS(0)
-cert	SSL-CERT	subject = test.tbsol.de	SUCCESS(0)
-cert	SSL-CERT	serial = EA8628EF3B3A7F44	SUCCESS(0)
-cert	SSL-CERT	from = 2016-12-16 09:12	SUCCESS(0)
-cert	SSL-CERT	until = 2017-12-16 09:12	SUCCESS(0)
-cert	SSL-CERT	remain = 360d 21h	SUCCESS(0)
-cert	PEER-CERT	issuer = /CN=mp-ol6u3-devel.tbsol.de CA Cert	SUCCESS(0)
-cert	PEER-CERT	subject = test.tbsol.de CA Cert	SUCCESS(0)
-cert	PEER-CERT	serial = 9F3D8E05D8800F22	SUCCESS(0)
-cert	PEER-CERT	from = 2013-07-15 12:20	SUCCESS(0)
-cert	PEER-CERT	until = 2023-07-13 12:20	SUCCESS(0)

```

| -cert | PEER-CERT | remain = 2395d 23h | SUCCESS(0) |
| -cert | SSL-CA | issuer = /C=de/ST=de/O=amitego/CN=test.tbsol.de | SUCCESS(0) |
| -cert | SSL-CA | subject = test.tbsol.de | SUCCESS(0) |
| -cert | SSL-CA | serial = EA8628EF3B3A7F44 | SUCCESS(0) |
| -cert | SSL-CA | from = 2016-12-16 09:12 | SUCCESS(0) |
| -cert | SSL-CA | until = 2017-12-16 09:12 | SUCCESS(0) |
| -cert | SSL-CA | remain = 360d 21h | SUCCESS(0) |
-----

```

Integrity check with the parameter **-cert** shows the status of the both VISULOX PORTAL certificates. PEER-CERT and SSL-CERT.

The serials can be displayed on the local VISULOX GATEWAY with the command **visulox-gateway server list** and have to match with the serials of the VISULOX PORTAL certificates.

Integrity check shows a warning, when the lifetime is lower than 30 days or an error when the lifetime is expired.

### visulox integrity -disk

```
Please wait ...Integrity-Check: VISULOX EVALUATION / xdevelopment / development
```

```

-----
| option | cat          | info                                     | returnCode |
-----
| -disk  | Diskspace   | ok in base (base threshold at 2.0GB has 39.67GB) | SUCCESS(0) |
| -disk  | Diskspace   | ok in var (var threshold at 5.0GB has 39.67GB) | SUCCESS(0) |
| -disk  | Diskspace   | ok in data (data threshold at 20.0GB has 39.67GB) | SUCCESS(0) |
| -disk  | Diskspace   | ok                                           | SUCCESS(0) |
| -disk  | DB Partition | ok fileserver.tbsol.de:/home/users/xxx      | SUCCESS(0) |
| -disk  | DB Partition | needs atleast 157.30MB - has 39.67GB        | SUCCESS(0) |
-----

```

```
ExitCode: SUCCESS
```

Among the checks also the disk space for the database is checked. VLX\_DATADIR must have at least 2.5 of size of the database available because VACUUM creates a copy of the database.

For example: a 4GB database needs 6 GB free disk space. The disk space is checked with integrity check.

## 4.6.4 Troubleshooting

- **VISULOX PORTAL connect failure**

On servers, where VISULOX Service is installed together with VISULOX PORTAL Service, the connection to the VISULOX PORTAL Service can be checked with a small tool:

```
/opt/visulox/lib/utils/sgd.tcl check

Check connections

-----
|                               scottasessionid |                               scottasessionowner
|
-----
| test-ol6u5.tbsol.de:1434362892796:1108252004568201775 | {.../_ens/o=Tarantella System Objects/ou=Visulox/cn=test-ol6u5}
|
-----
```

The following command reinstalls the necessary VISULOX PORTAL Service components on the server and mostly fixes connection errors:

```
visulox portal attach
```

- **VISULOX PORTAL Service warnings**

More details can be found in visulox-integrity.log. The Java tuning values should be adjusted for the environment. Mostly, the following settings will be adequate:

- tuning-jvm-initial: 1024
- tuning-jvm-max: 2048
- tuning-jvm-scale: 150

Adjust the values, with:

```
visulox-portal config edit --tuning-jvm-initial 2048  
visulox-portal config edit --tuning-jvm-max 2048  
visulox-portal config edit --tuning-jvm-scale 150
```

The following VISULOX PORTAL Service default values should also be checked:

- sessions-timeout-always
- sessions-timeout-session
- webtop-session-idle-timeout

**i** Changes of VISULOX PORTAL Service configurations is known to VISULOX after "**visulox portal attach -portal**".

- **"Administrator is root" warning**

The warning can be disabled by adding a new administrator to VISULOX PORTAL:

**Add a user**

```
useradd <name of the new portal administrator>  
passwd <name of the new portal administrator>
```

#### Add the new administrator to the VISULOX PORTAL administrators

```
visulox-portal object edit --name "/o=tarantella system objects/cn=administrator" --user admin
```

#### After changes to the VISULOX PORTAL, VISULOX needs to be reregistered

```
visulox portal attach
```

Doing a VISULOX Integrity-Check again, the warning has disappeared. root can be removed from the administrators list.

- **event.sh and filecheck.sh missing**

The files event.sh.template and filecheck.sh.template in **/opt/visulox/tools/** must be copied to event.sh and filecheck.sh, if needed. The correct permission (**0550 / vlx:vlxgroup**) has to be set as well for these files.

```
cd /opt/visulox/tools
cp events.sh.template events.sh
cp filecheck.sh.template filecheck.sh
chown vlx: events.sh filecheck.sh
chmod 0550 events.sh filecheck.sh
```

## 5 Glossary

Expression	Description
<b>3PA</b>	Third Party Authentication / 3rd Party Authentication
<b>Access Branding</b>	With Access Branding it is possible to display different login page designs for different users according to their access point.
<b>Access Management</b>	Enhanced VISULOX Concept for administrating the access of users
<b>AD</b>	<b>A</b> ctive <b>D</b> irectory
<b>AIP</b>	<b>A</b> daptive <b>I</b> nternet <b>P</b> rotocol: Client communication protocol from the VISULOX PORTAL Service
<b>Ambiguous login</b>	The situation where an authentication mechanism has found more than one match for a user and cannot distinguish between them without further information from the user
<b>Annotation</b>	A short text, that can be entered before a recorded session is confirmed, during a recorded session or in VISULOX Cockpit / Archive for closed sessions
<b>API</b>	<b>A</b> pplication <b>P</b> rogramming <b>I</b> nterface
<b>Application server</b>	A server which provides applications, that can be accessed via the VISULOX PORTAL
<b>Application session</b>	See: <b>emulator session</b>

<b>Args</b>	The arguments an application is started with
<b>Assist / Assistance</b>	See: <b>Assisting Cooperation</b>
<b>Assisting cooperation</b>	Within the VISULOX Cockpit, the user can select an application and press assist to join the application. The owner of the application selects the cooperation mode
<b>Chapter</b>	A chapter equals 20 minutes film of a recorded session
<b>CLI</b>	<b>Command Line Interface</b>
<b>CMD</b>	The command / path an application is started with
<b>Cooperation</b>	When two or more users are watching or working with the same application in realtime on their own desktop
<b>Cooperation master</b>	The user, who has started the application (owner) will be the master of this application in a Cooperation
<b>Cooperation member</b>	A user, who is not owner of an application and who is not able to switch the cooperation modes
<b>Cooperation modes</b>	<p><b>On hold:</b> Member is assigned to a Cooperation, but does not participate</p> <p><b>Observe:</b> Member is able to watch the Cooperation application, but can not interact</p> <p><b>Interact:</b> Member can interact with the application</p>
<b>CP</b>	Short form for <b>Cooperation</b>

<b>Datastore</b>	Internal VISULOX PORTAL Service database, where all defined objects (users, hosts, applications) are stored. A VISULOX PORTAL Array replicates the datastore between all members simultaneously
<b>DMZ</b>	Demilitarized zone (Perimeter zone)
<b>DSI</b>	<b>Directory Service Integration</b>
<b>Dual Control</b>	Cooperation enforcing a real four-eye-principle
<b>ELU</b>	<b>Extended License Usage</b> - When ELU has expired, its not possible to start more recorders or display more users than allowed under MD / Status, max users / recorders
<b>Emulator session</b>	The running session, when an application is started with the Workspace on an application server
<b>Expect script</b>	VISULOX PORTAL connection script started during the launch of an application
<b>External DNS name</b>	The name by which an VISULOX PORTAL Server is known to a client device. A VISULOX PORTAL Server can have multiple external DNS names.
<b>File Exchange</b>	File Transfer web access for transferring files between a client and the Transit Zone for users without access to the VISULOX PORTAL
<b>File Transfer Client</b>	VISULOX Component for transferring files securely from Transit Zone to application servers and back
<b>Film</b>	Summary of the recorded chapters
<b>Forced authentication</b>	When VISULOX PORTAL prompts for a user name or password, by displaying an authentication dialog box For example, if a user holds down the Shift key when clicking on an application's link on the Workspace

<b>FQDN</b>	<b>Fully Qualified Domain Name</b> - The full name of a system, containing its hostname and its domain name. For example: portal.visulox.com, where portal is the hostname of a server, and visulox.com is the domain name
<b>Group Access</b>	Group Access is used to define an Access Policy for a specific list of users. This is needed when users are working together in a project and the project is represented by a group object in the repository
<b>Host object</b>	Host objects can be assigned to File Transit, Command Guard and Command Connect groups.
<b>Host Connect</b>	See: <b>VISULOX Command Connect / VISULOX Command Guard</b>
<b>IAR</b>	<b>Intelligent Array Routing</b>
<b>ICA</b>	<b>Independent Computing Architecture</b> : Client communication protocol from Citrix
<b>Integrity-Check</b>	Tool to check the VISULOX components and services
<b>Internal / external message</b>	The VISULOX Service supplies an external message for the login page and an internal message for the user's Workspace
<b>Kiosk mode</b>	VISULOX PORTAL display mode, where an application is displayed in full-screen
<b>LDAP</b>	<b>Lightweight Directory Access Protocol</b>
<b>LDAPS</b>	<b>Lightweight Directory Access Protocol over SSL</b> . Used for secure connections to an LDAP directory.
<b>LID</b>	Short form for <b>License ID</b> - Contains the date, the license started

<b>Management Console</b>	See: <b>VISULOX Cockpit</b>
<b>MFA</b>	<b>Multi Factor Authentication</b>
<b>Native Client</b>	A VISULOX PORTAL component that can be installed on client devices. The client maintains communication with the VISULOX PORTAL Server and is required to run applications The Native Client is provided by Oracle.
<b>NEP</b>	Short form for <b>Network Entry Point</b>
<b>Network Entry Point</b>	See: <b>RIP</b>
<b>NFS</b>	<b>Network File System</b>
<b>Notifications</b>	Implemented notification system for access, Workspace / File Transfer and emulator sessions in the VISULOX Services
<b>Object</b>	A self-contained entity, defined by a number of attributes and values. VISULOX PORTAL Objects have different types, such as an X application. The available attributes for each type are defined by a schema
<b>One Time Passcode</b>	The One Time Passcode is used for authentication and will become invalid after usage. A provided OTP is based on a secret key and the time via a smartphone APP
<b>Organization object</b>	A VISULOX PORTAL Object used to represent the top level of an organizational hierarchy. Organization objects can contain <b>OU=</b> or user profile objects. Organization objects have an <b>O=</b> naming attribute.

<b>Organizational hierarchy</b>	The collection of objects in the VISULOX PORTAL Datastore, descending from one or more organization or domain component objects. Represents the collection of people, application servers, and applications within an organization.
<b>Organizational unit object</b>	A VISULOX PORTAL Object used to distinguish different departments, sites, or teams in an organizational hierarchy. Organizational unit ( <b>OU</b> ) objects can be contained in an organization or domain component object. Organizational unit objects have an <b>OU=</b> naming attribute
<b>OTP</b>	Short form for <b>One Time Passcode</b>
<b>Peer DNS name</b>	The name by which an VISULOX PORTAL Server is known to other VISULOX PORTAL Servers in the same array
<b>Primary server</b>	The VISULOX PORTAL Server that acts as the authoritative source for global information, and maintains the definitive copy of the VISULOX PORTAL Datastore
<b>RDP</b>	<b>Remote Desktop Protocol</b> : Client communication protocol from Microsoft
<b>Remote IP</b>	Remote IP address, the information, from where a client request is coming
<b>Report</b>	The VISULOX Service is collecting data about workspacesessions, emulatorsessions, recordings and cooperations. The information can be clearly arranged in reports. In VISULOX Cockpit a variety of possible reports can be created on several pages
<b>Resume</b>	To redisplay an application session that has been suspended. See also: <b>suspend</b>
<b>RIP</b>	Short form for <b>Remote IP</b> address
<b>RVA</b>	<b>Remote Vendor Access</b>

<b>S &amp; M</b>	Short form for <b>S</b> upport and <b>M</b> aintenance
<b>Secondary server</b>	An array member that is not the primary server. The primary server replicates information to secondary servers.
<b>Session</b>	The VISULOX PORTAL generates a session for any X11 or RDP application, which has an unique session ID
<b>SIEM</b>	<b>S</b> ecurity <b>I</b> nformation and <b>E</b> vent <b>M</b> anagement
<b>SOX</b>	Short form for <b>S</b> arbanes- <b>O</b> xley <b>A</b> ct
<b>SSL certificate</b>	A digital passport that establishes credentials on the web. In VISULOX PORTAL Service, allows client devices to trust the identity of a VISULOX PORTAL Server
<b>Suspend</b>	To pause an application session. A suspended application is not closed, it can be resumed. See also: <b>resume</b>
<b>TAP</b>	Short form for <b>T</b> emporary <b>A</b> ccess <b>P</b> IN, part of the Multi Factor Authentication (MFA)
<b>TCC</b>	Short form for <b>T</b> arantella <b>C</b> lient <b>C</b> omponent: Component for login into the VISULOX PORTAL via <b>Native Client</b>
<b>TCL</b>	Programming Language. Most of the VISULOX products are based on TCL
<b>Temporary Access PIN</b>	VISULOX method for the Multi Factor Authentication ( <b>MFA</b> )
<b>TFN</b>	Tarantella Full Naming, X.500 format to address a VISULOX PORTAL object
<b>Transit Zone</b>	Zone, where files are transferred from/to application servers/clients

<b>VAP</b>	Short form for <b>Virtual Access Point</b>
<b>Virtual Access Point</b>	VISULOX method to get an independent URL of the VISULOX Access Nodes for reliability and Workspace balancing
<b>VISULOX Access Node</b>	Node running the VISULOX PORTAL Service and the VISULOX Service
<b>VISULOX Base</b>	Single VISULOX Node
<b>VISULOX Cluster</b>	Two or more VISULOX Nodes, that are joined together because of scalability, redundancy and load balancing
<b>VISULOX Cockpit</b>	Central VISULOX application to control sessions, access, recording, cooperations and to generate reports
<b>VISULOX Command Connect</b>	VISULOX component, which provides the possibility to connect to multiple hosts and to open an X-Client on these hosts. The connection method can be SSH, RDP or telnet. Former: <b>Host Connect</b>
<b>VISULOX Command Guard</b>	VISULOX component, which provides the possibility to connect to multiple hosts and to open an X-Client on these hosts Command Guard has command level controls for the application. It allows and denies the usage of certain commands by the user Additionally server side scripts can be issued either to multiple endpoints or to a single one
<b>VISULOX Common Access Platform</b>	The whole environment, that is built with the VISULOX GATEWAY, VISULOX Portal Service, VISULOX Service and databases
<b>VISULOX Data</b>	VISULOX Database and VISULOX Filestore

<b>VISULOX Filestore</b>	File system which stores the films. 5 MByte per user and per hour. Recommended for VISULOX is a local disk with 150-250 GB, for VISULOX Archive Node depending on the lifetime of films, up to x TB on a NAS/SAN storage
<b>VISULOX GATEWAY</b>	The VISULOX GATEWAY is a proxy server designed to be deployed in front of a VISULOX PORTAL Array in a demilitarized zone (DMZ). This enables the VISULOX PORTAL Array to be located on the internal network of an organization. Additionally, all connections can be authenticated in the DMZ before any connections are made to the VISULOX PORTAL servers in the array. The VISULOX GATEWAY manages load balancing of HTTP connections for the VISULOX PORTAL Servers in the array.
<b>VISULOX Host Connect</b>	See: <b>VISULOX Command Connect</b>
<b>VISULOX Hotfix</b>	Tool to check the software status in the cluster, backup and apply hotfixes
<b>VISULOX keystroke recording with analyzing engine</b>	In this recording mode all user keyboard interactions are registered and can be checked for unwanted entries (analyzing engine)
<b>VISULOX Node</b>	Node running the VISULOX Service to control sessions, films and recorders
<b>VISULOX PAM</b>	<b>VISULOX Privileged Access Management</b>
<b>VISULOX PORTAL Array</b>	Two or more VISULOX Access Nodes, that are joined together because of scalability, redundancy and load balancing
<b>VISULOX PORTAL Benchmark</b>	Tool to create a defined number of demo-users, who log into the VISULOX PORTAL and start recorded applications automatically. All settings can be configured easily within a GUI
<b>VISULOX PORTAL Console</b>	Web-based management console for the VISULOX PORTAL Service (Former: Administration Console)

<b>VISULOX PORTAL Web Server</b>	A pre-built web server installed and configured along with the VISULOX PORTAL Service, contains Apache, mod_ssl for HTTPS support, and Tomcat for Java Servlet and JSP support
<b>VISULOX PORTAL Web Services</b>	An API collection that allows developers to build their own applications to work with the VISULOX PORTAL Service. The APIs can be used to authenticate users, launch applications, and interact with the VISULOX PORTAL Datastore
<b>VISULOX Revision Server</b>	VISULOX Node which replicates the production database into Revision Server database and transfers the films from the production filestore into the Revision Server filestore (also known as Archive Server)
<b>VISULOX Service Group</b>	See: <b>VISULOX Cluster</b>
<b>VISULOX Short Support Report</b>	A Short Support Report to send via eMail created with <b>visulox support -info</b> . The Short Support Report should be sent to the VISULOX Support Team every time a new Support Request is opened
<b>VISULOX Support Report</b>	Package generated by the <b>visulox support</b> command, containing all information, necessary for support
<b>VISULOX Transit Area</b>	File Transfer component embedded in the Workspace to transfer files between client and Transit Zone
<b>VISULOX Transit Mapping</b>	To setup the VISULOX Transit Zone on Unix application servers, that are not a VISULOX Node, an RPM file is available for installation.
<b>VISULOX Videolog Player</b>	Player to view the recorded films inside the VISULOX Cockpit or checked out films in a browser
<b>VISULOX Webservice User</b>	Each VISULOX Service needs this user in the datastore to read the webservices on the VISULOX Access Nodes. The VISULOX webservice user has to be setup once in the datastore
<b>VISULOX_Setup.xls</b>	Excel-sheet, which has to be filled out in the planning phase by the responsible project leader, together with the amitego consultant

<b>vlxMode</b>	VISULOX variable set in the VISULOX PORTAL Console
<b>VLX Password SelfService</b>	Active Directory (AD) and Oracle Unified Directory (OUD) users are able to change their password by themselves with this application assigned.
<b>Webtop</b>	In the current version, the Webtop is called the <b>Workspace</b> . A Workspace is the term used to describe a user's applications, documents, and desktops. See: <b>Workspace</b>
<b>WM</b>	Short form for <b>Window Manager</b>
<b>Workspace</b>	The Workspace is displayed after logging into the VISULOX PORTAL. It is a special web page, that lists the applications that are assigned to the user
<b>Workspace balancing</b>	VISULOX load balancing mechanism including a virtual access point
<b>Workspace session</b>	The running session, after a user has logged into the VISULOX PORTAL via browser or Native Client
<b>X11 forwarding</b>	The process of forwarding, or tunneling, the windows of a remotely started X application to a client desktop
<b>X Window System</b>	A distributed window system for UNIX platform operating systems, based on the X11 protocol. Also called X11, or X Windows
<b>X.509 certificate</b>	See: <b>SSL certificate</b>